



XEN Fully Virtualized

Installation Guide

UPDATED: 27 July 2023

Copyright Notices

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

These materials and all Progress® software products are copyrighted and all rights are reserved by Progress Software Corporation. The information in these materials is subject to change without notice, and Progress Software Corporation assumes no responsibility for any errors that may appear therein. The references in these materials to specific platforms supported are subject to change.

#1 Load Balancer in Price/Performance, 360 Central, 360 Vision, Chef, Chef (and design), Chef Habitat, Chef Infra, Code Can (and design), Compliance at Velocity, Corticon, Corticon.js, DataDirect (and design), DataDirect Cloud, DataDirect Connect, DataDirect Connect64, DataDirect XML Converters, DataDirect XQuery, DataRPM, Defrag This, Deliver More Than Expected, DevReach (and design), Driving Network Visibility, Flowmon, Inspec, Ipswitch, iMacros, K (stylized), Kemp, Kemp (and design), Kendo UI, Kinvey, LoadMaster, MessageWay, MOVEit, NativeChat, OpenEdge, Powered by Chef, Powered by Progress, Progress, Progress Software Developers Network, SequeLink, Sitefinity (and Design), Sitefinity, Sitefinity (and design), Sitefinity Insight, SpeedScript, Stylized Design (Arrow/3D Box logo), Stylized Design (C Chef logo), Stylized Design of Samurai, TeamPulse, Telerik, Telerik (and design), Test Studio, WebSpeed, WhatsConfigured, WhatsConnected, WhatsUp, and WS_FTP are registered trademarks of Progress Software Corporation or one of its affiliates or subsidiaries in the U.S. and/or other countries.

Analytics360, AppServer, BusinessEdge, Chef Automate, Chef Compliance, Chef Desktop, Chef Workstation, Corticon Rules, Data Access, DataDirect Autonomous REST Connector, DataDirect Spy, DevCraft, Fiddler, Fiddler Classic, Fiddler Everywhere, Fiddler Jam, FiddlerCap, FiddlerCore, FiddlerScript, Hybrid Data Pipeline, iMail, InstaRelinker, JustAssembly, JustDecompile, JustMock, KendoReact, OpenAccess, PASOE, Pro2, ProDataSet, Progress Results, Progress Software, ProVision, PSE Pro, Push Jobs, SafeSpaceVR, Sitefinity Cloud, Sitefinity CMS, Sitefinity Digital Experience Cloud, Sitefinity Feather, Sitefinity Thunder, SmartBrowser, SmartComponent, SmartDataBrowser, SmartDataObjects, SmartDataView, SmartDialog, SmartFolder, SmartFrame, SmartObjects, SmartPanel, SmartQuery, SmartViewer, SmartWindow, Supermarket, SupportLink, Unite UX, and WebClient are trademarks or service marks of Progress Software Corporation and/or its subsidiaries or affiliates in the U.S. and other countries. Java is a registered trademark of Oracle and/or its affiliates. Any other marks contained herein may be trademarks of their respective owners.

Please refer to the NOTICE.txt or Release Notes – Third-Party Acknowledgements file applicable to a particular Progress product/hosted service offering release for any related required third-party acknowledgements.

Table of Contents

1 Introduction	4
2 Installing Virtual LoadMaster (VLM) on a Xen Environment	6
2.1 Download the Xen, Fully-Virtualized, Files	6
2.2 Deploy the LoadMaster	7
2.3 Check the Virtual Machine Settings	8
2.4 LoadMaster IP Address	8
2.5 License and Configure the LoadMaster	8
3 Troubleshooting and Notes	14
3.1 Configuring the LoadMaster Using the Console	14
3.2 Factory Reset	16
3.3 Items of Note	16
4 References	18
Licensing, Feature Description	18
Last Updated Date	19

1 Introduction

The Kemp Virtual LoadMaster is a version of the Kemp LoadMaster that runs as a virtual machine within a hypervisor and can provide all the features and functions of a hardware-based LoadMaster.

This document describes the installation of the Virtual LoadMaster (VLM) within a Xen, fully-virtualized environment.

The VLM has been tested with Xen.org versions 3.1, 4.0 and 4.1.

There are several different versions of the VLM available. Full details of the currently supported versions are available on our website: www.kemptechnologies.com.

The Xen virtual machine guest environment for the VLM, at minimum, must include:

- 2 x virtual processors
- 2 GB RAM
- 16 GB virtual hard disk capacity (sparse where possible)

Full virtualization provides total abstraction of the underlying physical system. No modification of the guest OS or application is required. The guest OS or applications do not realize they are in a virtual environment.

In tests, the Xen para-virtualized VLM had much better performance levels than the Xen fully-virtualized VLM

There may be maximum configuration limits imposed by Xen such as maximum RAM per VM, Virtual NICs per VM etc. For further details regarding the configuration limits imposed by Xen, please refer to the relevant Xen documentation.

A wide variety of Linux distributions can be used as the Dom0 operating system. For a full list of the compatible Linux distributions, please refer to www.xen.org.

Kemp LoadMaster has been tested with the following Dom0 operating systems and versions of Xen.org.

Dom0 OS	Xen.org Version
OpenSUSE 12.1	3.1

1 Introduction

Dom0 OS	Xen.org Version
OpenSUSE 11.4	4.0.2
Debian 6.0	4.1
CentOS 6.3	4.1

If you have any issues with the Virtual LoadMaster when using a different combination of Xen.org versions and Linux distributions as the Dom0, then please contact Kemp Support.

2 Installing Virtual LoadMaster (VLM) on a Xen Environment

The following instructions describe how to install a Virtual LoadMaster on a Xen environment.

2.1 Download the Xen, Fully-Virtualized, Files

The VLM is packaged within a .tar.gz file for ease of deployment. This file can be freely downloaded from Kemp for a 30 day evaluation period. To download the VLM please follow the instructions below:

1. Go to <http://www.kemptechnologies.com/try>.
2. Click the **Download Now** button.
3. Within the **Select your hypervisor** section, select the option for **Xen**.
4. Select your country from the drop-down list provided.
5. Read the End User License Agreement.
6. To proceed with the download, ensure the **I agree to the End User License Agreement terms** check box is ticked.
7. Click the **Download** button.
8. Unzip the contents of the file to an accessible location within the Xen environment. The .zip file contains the following files, where x.x-xx denotes the release number:

- **Installation_Guide-KVM.pdf**
- **Installation_Guide-XEN_Fully_Virtualized.pdf**
- **LoadMaster-VLM-7.2.36.2.14271.RELEASE-Linux-KVM-XEN.tar.gz**: a zip file containing the disk image
- **LoadMaster-VLM-7.2.36.2.14271.RELEASE-Linux-KVM-XEN.tar.gz.checksum.xml**
- **LoadMaster-VLM-7.2.36.2.14271.RELEASE-Linux-KVM-XEN.tar.gz.md5**
- **LoadMaster-VLM-7.2.36.2.14271.RELEASE-Linux-KVM-XEN.tar.gz.sha**

2.2 Deploy the LoadMaster

Kemp recommends using Virtual Machine Manager to deploy the LoadMaster. The steps below were documented using Virtual Machine Manager:

1. Click the Create a new virtual machine button.
2. Enter a **Name** for the Virtual Machine.

The name cannot contain any spaces.

3. Select **Import existing disk image**.
4. Click **Forward**.
5. Click **Browse**.
6. Browse to and select the disk file.
7. Select **Linux** as the **OS type**.
8. In the **Version** drop-down list, scroll to the bottom and click **Show all OS options**.
9. Click the **Version** drop-down list again. Scroll to the bottom and select **Generic 2.6.25 or later with virtio**.
10. Click **Forward**.
11. Click **Virtualization Method**.
12. Select **Full Virtualization or HVM**.
13. Click **Apply**.
14. Enter a minimum of **2048** MB in the **Memory** text box.
15. Enter a minimum of **2** in the **CPUs** text box.
16. Click **Forward**.
17. Tick the **Customize configuration before install** check box.
18. Expand the **Advanced options** section.
19. Make any amendments to this section, as needed.
20. Click **Finish**.
21. Click the **Disk** option on the left.

2 Installing Virtual LoadMaster (VLM) on a Xen Environment

22. Expand the **Advanced Options** section.
23. Select **Virtio** as the **Disk bus**.
24. Click the **NIC** option on the left.
25. Click **Yes** to apply the changes.
26. Select **virtio** as the **Device model**.
27. Change any other settings as needed.
28. Click **Apply**.
29. Click **Begin Installation**.

2.3 Check the Virtual Machine Settings

Please verify that the Virtual Machine settings are configured with the recommended values:

- 2 x virtual processors
- 2 GB RAM
- 16 GB virtual hard disk capacity (sparse where possible)

2.4 LoadMaster IP Address

```
#
# Your LoadMaster has finished booting.
# UUID: bed15b0f-cd9a-4517-b95e-a11d080b3d89
# Serial Number: 1050976
# IP address of LoadMaster is 10.154.11.170
#
# Point your browser at https://10.154.11.170 to configure your LoadMaster.
#
#####
```

The VLM should obtain an IP address using DHCP. Make a note of this address.

If the VLM does not obtain an IP address, or if the IP address needs to be changed, it can be manually configured in the console by following the steps in the **Configuring the LoadMaster Using the Console** section.

2.5 License and Configure the LoadMaster

The LoadMaster must now be configured to operate within the network configuration.

1. In an internet browser, enter the IP address that was previously noted.

2 Installing Virtual LoadMaster (VLM) on a Xen Environment


Ensure to enter **https://** before the IP address.

2. A warning may appear regarding website security certificates. Please click the continue/ignore option.

3. The LoadMaster End User License Agreement screen appears.

Please read the license agreement and, if you are willing to accept the conditions therein, click on the **Agree** button to proceed.

4. A screen appears asking if you are OK with the LoadMaster regularly contacting Kemp to check for updates and other information. If you are OK with this, click **Continue** to proceed. If you want to disable this functionality, remove the check from the **Enable Call Home** check box and click **Continue** to proceed.




5. If using the **Online** licensing method, fill out the fields and click **License Now**.

If you are starting with a trial license, there is no need to enter an Order ID. If you are starting with a permanent license, enter the Kemp **Order ID#** if this was provided to you.

If using the **Offline Licensing** method, select **Offline Licensing**, obtain the license text, paste it into the **License** field and click **Apply License**.

2 Installing Virtual LoadMaster (VLM) on a Xen Environment

For detailed instructions on how to register for a Kemp ID and license the LoadMaster, refer to the **Licensing, Feature Description** on the [Kemp Documentation Page](#).



6. If you entered an **Order ID**, a screen appears that provides a list of available licenses for that order ID, in addition to any licenses registered for the Kemp ID based on the LoadMaster platform type. Select the license type you want to apply to this LoadMaster.


If the license type you want is not displayed, please contact your Kemp representative.

7. Click **Continue**.

8. The login screen appears, enter the **bal** user name and the password.

9. In the screen informing you that the password has changed, press the **Continue** button.

10. If your machine has shipped with a temporary license you should get a warning informing you that a temporary license has been installed on your machine and for how long the license is valid.



11. Click **OK**.

12. You should now connect to the **Home** screen of the LoadMaster.

Last Login: Mon Dec 5 13:38:34 UTC 2016 from 10.0.30.86
111 Successful logins in last 30 days

IP address

10.154.11.180

LoadMaster Version

7.2.37.0.14221.DEV.20161129-1027

Serial Number

446312

Boot Time

Mon Dec 5 11:32:33 UTC 2016

- 13. Go to **System Configuration > Network Setup** in the main menu.
- 14. Click the **eth0** menu option within the **Interfaces** section.

Network Interface 0

Interface Address (address[/prefix])

Set Address

Link Status

Speed: 10000Mb/s, Full Duplex

Automatic

Force Link

MTU:

1500

Set MTU

Additional addresses (address[/prefix])

Add Address

VLAN Configuration

Interface Bonding

- 15. In the **Network Interface 0** screen, enter the IP address of the eth0 interface, the network facing interface of the LoadMaster, in the **Interface Address** input field.
- 16. Click the **Set Address** button.
- 17. Click the **eth1** menu option within the **Interfaces** section.
- 18. In the **Network Interface 1** screen, enter the IP address of the eth1 interface, the farm-side interface of the LoadMaster, in the **Interface Address** input field.
- 19. Click on the **Set Address** button.

This interface is optional, depending on the network configuration.

- 20. Click on the **Local DNS Configuration > Hostname Configuration** menu option.

Set Hostname

Hostname

Set Hostname

2 Installing Virtual LoadMaster (VLM) on a Xen Environment

21. In the **Hostname configuration** screen, enter the hostname into the **Current Hostname** input field.
22. Click the **Set Hostname** button.
23. Click the **Local DNS Configuration > DNS Configuration** menu option.

DNS Servers

DNS NameServer (IP Address)
Operation

10.154.75.25	Delete
--------------	--------

Add Nameserver

IP Address
Add

Add Search Domain

Domain
Add

24. In the **DNS configuration** screen, enter the IP address(es) of the DNS Server(s) which is used to resolve names locally on the LoadMaster into the **DNS NameServer** input field.
25. Click the **Add** button.
26. Enter the domain name that is to be prepended to requests to the DNS nameserver into the **DNS NameServer** input field.
27. Click the **Add** button.
28. Click the **System Configuration > Network Setup > Default Gateway** menu option.

The IPv4 default gateway must be on the 10.154.0.0/16 network

IPv4 Default Gateway Address
Set IPv4 Default Gateway

29. In the **DNS configuration** screen, enter the IP address of the default gateway into the **IPv4 Default Gateway Address** input field.
- If you have an IPv6 Default Gateway, please enter the value in the **IPv6 Default Gateway Address** input field.
30. Click the **Set IPv4 Default Gateway** button.

2 Installing Virtual LoadMaster (VLM) on a Xen Environment

The LoadMaster is now fully installed and ready to be used. For further information on how to configure and implement the Virtual LoadMaster, please refer to the LoadMaster documentation which can be downloaded from the <http://kemptechnologies.com/documentation> page.


3 Troubleshooting and Notes

3.1 Configuring the LoadMaster Using the Console


If the LoadMaster does not automatically obtain an IP address using DHCP, or if the user prefers to configure the LoadMaster using the console, then the following configuration steps must be completed before starting the LoadMaster.

1. Login into the LoadMaster using the console with the following settings:

- **lb100 login:** bal
- **Password:** 1fourall





2. Enter the IP address of the eth0 interface, the network facing interface of the LoadMaster, in the input field within the **Network Side Interface Address** dialog box.
3. Press **OK**.




4. Enter the IP address of the default gateway in the input field of the **Default Gateway** dialog box.
5. Press **OK**.
6. Once these are set, a prompt will appear asking to connect to the web interface at the newly configured IP address. In an internet browser enter the IP address of the eth0 entered in Step 2.

Ensure to enter **https://** before the IP address.

7. A warning may appear regarding website security certificates. Please click the continue/ignore option.
8. The LoadMaster End User License Agreement screen appears.
9. Please read the license agreement and, if willing to accept the conditions therein, click on the **Agree** button to proceed.
10. If the machine has shipped with a temporary license, a warning will appear informing that a temporary license has been installed on the machine and for how long the license is valid.
11. Click **OK**.
12. The Appliance Vitals screen of the LoadMaster should appear.

IP address	10.154.11.51 (lb100:10.154.11.50)
Serial Number	1050788
Boot Time	Tue Sep 8 09:30:58 UTC 2015
Active Since	Tue Sep 8 09:31:13 UTC 2015
LoadMaster Version	7.1-29-1851.20150907-1730
License	UUID: 6987ad8c-ff52-4158-acbb-372a07faa13d Activation date: Thu Aug 20 09:04:46 UTC 2015 Licensed until: September 20 2015 Support Level: Evaluation + WAF Support Until: Sat Aug 20 04:00:00 UTC 2016 License Type: VLM-5000 ESP GEO License Status: Single Temp Appliance Model: VLM-5000G+
CPU Load	2% 
TPS	Total 0 (SSL 0)
WAF Stats	Total handled: 0 Incidents: 0
NetLoad	Mbits/sec
eth0	0.0 

 Upgrade ↗

The LoadMaster is now fully installed and ready to be used. For further information on how to configure and implement the Virtual LoadMaster, please refer to the LoadMaster documentation which can be found here: <https://kempttechnologies.com/documentation>.

3.2 Factory Reset

If you perform a factory reset on your VLM, all configuration data, including the VLM's IP address is deleted. During the subsequent reboot the VLM attempts to obtain an IP address using DHCP. If the VLM is on a different subnet to the DHCP server then an IP address will not be obtained and the IP address is set to the default 192.168.1.101.

The VLM may not be accessible using this address. If this is the case then you must run through the quick setup using the console as described in the **Configuring the LoadMaster Using the Console** section.

3.3 Items of Note

The following are some items to note when using LoadMaster in a Xen environment.

- A filename may not match the running DomU name. Do an XM list to get the DomU name.

- Xen VM's can be administered "locally" by either emulated serial, using xm console OR emulated VGA using VNC
- Usually the customer will have a bridge for networking, /dev/br0 or br1, etc. A VM will not start unless their networking is perfect.
- Xen logs are located in:
 - /var/log/xen/qemu-dm-LoadMaster_VLM.log
 - /var/log/xen/xend.log

4 References

Unless otherwise specified, the below documents can be found at <http://kemptechnologies.com/documentation>.

Licensing, Feature Description

Last Updated Date

This document was last updated on 27 July 2023.