

MOVEit Transfer

Deployment Guide

UPDATED: 27 July 2023

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

These materials and all Progress® software products are copyrighted and all rights are reserved by Progress Software Corporation. The information in these materials is subject to change without notice, and Progress Software Corporation assumes no responsibility for any errors that may appear therein. The references in these materials to specific platforms supported are subject to change.

#1 Load Balancer in Price/Performance, 360 Central, 360 Vision, Chef, Chef (and design), Chef Habitat, Chef Infra, Code Can (and design), Compliance at Velocity, Corticon, Corticon.js, DataDirect (and design), DataDirect Cloud, DataDirect Connect, DataDirect Connect64, DataDirect XML Converters, DataDirect XQuery, DataRPM, Defrag This, Deliver More Than Expected, DevReach (and design), Driving Network Visibility, Flowmon, Inspec, Ipswitch, iMacros, K (stylized), Kemp, Kemp (and design), Kendo UI, Kinvey, LoadMaster, MessageWay, MOVEit, NativeChat, OpenEdge, Powered by Chef, Powered by Progress, Progress, Progress Software Developers Network, SequeLink, Sitefinity (and Design), Sitefinity, Sitefinity (and design), Sitefinity Insight, SpeedScript, Stylized Design (Arrow/3D Box logo), Stylized Design (C Chef logo), Stylized Design of Samurai, TeamPulse, Telerik, Telerik (and design), Test Studio, WebSpeed, WhatsConfigured, WhatsConnected, WhatsUp, and WS_FTP are registered trademarks of Progress Software Corporation or one of its affiliates or subsidiaries in the U.S. and/or other countries.

Analytics360, AppServer, BusinessEdge, Chef Automate, Chef Compliance, Chef Desktop, Chef Workstation, Corticon Rules, Data Access, DataDirect Autonomous REST Connector, DataDirect Spy, DevCraft, Fiddler, Fiddler Classic, Fiddler Everywhere, Fiddler Jam, FiddlerCap, FiddlerCore, FiddlerScript, Hybrid Data Pipeline, iMail, InstaRelinker, JustAssembly, JustDecompile, JustMock, KendoReact, OpenAccess, PASOE, Pro2, ProDataSet, Progress Results, Progress Software, ProVision, PSE Pro, Push Jobs, SafeSpaceVR, Sitefinity Cloud, Sitefinity CMS, Sitefinity Digital Experience Cloud, Sitefinity Feather, Sitefinity Thunder, SmartBrowser, SmartComponent, SmartDataBrowser, SmartDataObjects, SmartDataView, SmartDialog, SmartFolder, SmartFrame, SmartObjects, SmartPanel, SmartQuery, SmartViewer, SmartWindow, Supermarket, SupportLink, Unite UX, and WebClient are trademarks or service marks of Progress Software Corporation and/or its subsidiaries or affiliates in the U.S. and other countries. Java is a registered trademark of Oracle and/or its affiliates. Any other marks contained herein may be trademarks of their respective owners.

Please refer to the NOTICE.txt or Release Notes – Third-Party Acknowledgements file applicable to a particular Progress product/hosted service offering release for any related required third-party acknowledgements.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

Table of Contents

1 Introduction **4**

1.1 Document Purpose 4

1.2 Intended Audience 4

2 Template **5**

3 Architecture **6**

4 Configure the LoadMaster **7**

4.1 Disable Server NAT Globally 7

5 Virtual Services **8**

5.1 Create the MOVEit Transfer HTTPS Virtual Service 8

5.1.1 MOVEit Transfer HTTPS Virtual Service Recommended API Settings (optional) 9

5.2 Create the MOVEit SFTP Virtual Services 9

5.2.1 MOVEit Transfer SFTP Virtual Service Recommended API Settings (optional) 10

5.3 Create the MOVEit FTPS Virtual Services 10

5.3.1 MOVEit Transfer FTPS Virtual Service Recommended API Settings (optional) 11

Last Updated Date **13**

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

1 Introduction

Progress MOVEit provides secure file transfers of sensitive data to meet regulatory compliance for every organization. With advanced management, automation, flexible deployment options, reporting, and simple API integrations, Progress MOVEit is the secure file transfer of choice.

The LoadMaster delivers an exceptional, cost effective, and easy to use solution which, by employing intelligent server health checking, High Availability (HA) and load balancing to provides an always-on application experience for MOVEit Transfer.

1.1 Document Purpose

This document provides the recommended LoadMaster settings used when providing load balancing for MOVEit Transfer. The Kemp Support team is available to provide solutions for scenarios not explicitly defined. The Kemp Support site can be found at: https://support.kemptechnologies.com.

1.2 Intended Audience

This document is intended to be read by anyone who is interested in configuring the LoadMaster to optimize Progress MOVEit Transfer.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

2 Template

Kemp has developed a template containing our recommended settings for this workload. You can install this template to help create Virtual Services (VSs) because it automatically populates the settings. You can use the template to easily create the required VSs with the recommended settings. For some workloads, additional manual steps may be required such as assigning a certificate or applying port following. These steps are covered in the document, if needed.

You can remove templates after use and this will not affect deployed services. If needed, you can make changes to any of the VS settings after using the template.


Download released templates from the following page: LoadMaster Templates.

For more information and steps on how to import and use templates, refer to the Virtual Services and Templates, Feature Description on the Kemp Documentation page.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

3 Architecture

Progress MOVEit Transfer deployments consist of two or more secure file transfer servers and a load balancer to provide the needed high availability, health checking, and distribution of traffic.



© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

4 Configure the LoadMaster

Refer to the sections below for details on some recommended global settings.

4.1 Disable Server NAT Globally

Layer 4 load balancing requires that the MOVEit servers point their default gateway to the load balancer to avoid any asymmetrical routing. In a single LoadMaster deployment this would be the interface IP address of the load balancer and in a HA pair configuration, this would be the shared IP address.

> Because all egress traffic will be sent out of the load balancer, Server NAT should be disabled globally to not interfere with required connectivity to other services. This setting should be disabled with caution should there be other workloads published on the same load balancer.

To disable **Server NAT (SNAT)** globally, follow the steps below:

1. In the main menu of the LoadMaster User Interface (UI), go to **System Configuration > Miscellaneous Options > Network Options**.
2. Deselect the **Enable Server NAT** check box.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

5 Virtual Services

MOVEit Transfer supports several secure protocols that can be load balanced and failover automatically in the event of a server going offline.


This step-by-step setup of Virtual Services (VSs) leverages the Kemp application template for MOVEit Transfer. This template configures the Virtual Services to leverage Layer 4 and/or Layer 7 transparency for the TCP services such as HTTPS, SFTP, and FTPS. This approach will allow the real servers to see the source IP address of the devices running in the infrastructure.

The table in each section outlines the settings configured by the application template. You can use this information to manually configure Virtual Services or use the Kemp LoadMaster Application Programming Interface (API) and automation tools.

5.1 Create the MOVEit Transfer HTTPS Virtual Service

The following are the steps involved and the recommended settings to configure the MOVEit Transfer HTTPS Virtual Service.

1. In the main menu of the LoadMaster User Interface (UI), go to **Virtual Services > Add New**.



2. Type a valid **Virtual Address**.
3. Select the **MOVEit-Transfer-HTTPS** template in the **Use Template** drop-down list.
4. Click **Add this Virtual Service**.
5. Expand the **Real Servers** section.
6. Click **Add New**.
7. Type the **Real Server Address**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

8. Click **Add This Real Server**.
9. Repeat these steps to add more Real Servers as needed.

5.1.1 MOVEit Transfer HTTPS Virtual Service Recommended API Settings (optional)

This table outlines the API parameters and values set using the Kemp application template. You can use these settings with scripts and automation tools.


API Parameter	API Value
port	443
prot	tcp
VStype	http
Transparent	1
Schedule	lc
CheckType	tcp
CheckPort	443

It is optional to add a HTTP redirector Virtual Service. Whether you require one or not depends on your environment.

5.2 Create the MOVEit SFTP Virtual Services

The following are the steps involved and the recommended settings to configure the MOVEit Transfer SFTP Virtual Service:

1. In the main menu of the LoadMaster UI, go to **Virtual Services > Add New**.



2. Type a valid **Virtual Address**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

3. Select the **MOVEit-Transfer-SFTP** template in the **Use Template** drop-down list.
4. Click **Add this Virtual Service**.
5. Expand the **Real Servers** section.
6. Click **Add New**.
7. Type the **Real Server Address**.
8. Click **Add This Real Server**.
9. Repeat these steps to add more Real Servers as needed.

5.2.1 MOVEit Transfer SFTP Virtual Service Recommended API Settings (optional)

This table outlines the API parameters and values set using the Kemp application template. You can use these settings with scripts and automation tools.


API Parameter	API Value
port	22
prot	tcp
VStype	gen
Transparent	1
Schedule	lc
CheckType	tcp
CheckPort	22

5.3 Create the MOVEit FTPS Virtual Services

The following are the steps involved and the recommended settings to configure the MOVEit Transfer FTPS Virtual Service:

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

1. In the main menu of the LoadMaster UI, go to **Virtual Services > Add New**.



2. Type a valid **Virtual Address**.
3. Select the **MOVEit-Transfer-FTPS** template in the **Use Template** drop-down list.
4. Click **Add this Virtual Service**.
5. Expand the **Real Servers** section.
6. Click **Add New**.
7. Type the **Real Server Address**.
8. Click **Add This Real Server**.
9. Repeat these steps to add more Real Servers as needed.

5.3.1 MOVEit Transfer FTPS Virtual Service Recommended API Settings (optional)

This table outlines the API parameters and values set using the Kemp application template. You can use these settings with scripts and automation tools.

API Parameter	API Value
port	21
prot	tcp
VStype	gen
Transparent	1
ServerInit	3
ExtraPorts	990,10021,10990,3000-3100
Schedule	lc

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

Persist	Src
PersistTimeout	300
CheckType	tcp
CheckPort	21

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

Last Updated Date

This document was last updated on 27 July 2023.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.