

LoadMaster for Open Telekom Cloud

Installation Guide

UPDATED: 27 July 2023

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

These materials and all Progress® software products are copyrighted and all rights are reserved by Progress Software Corporation. The information in these materials is subject to change without notice, and Progress Software Corporation assumes no responsibility for any errors that may appear therein. The references in these materials to specific platforms supported are subject to change.

#1 Load Balancer in Price/Performance, 360 Central, 360 Vision, Chef, Chef (and design), Chef Habitat, Chef Infra, Code Can (and design), Compliance at Velocity, Corticon, Corticon.js, DataDirect (and design), DataDirect Cloud, DataDirect Connect, DataDirect Connect64, DataDirect XML Converters, DataDirect XQuery, DataRPM, Defrag This, Deliver More Than Expected, DevReach (and design), Driving Network Visibility, Flowmon, Inspec, Ipswitch, iMacros, K (stylized), Kemp, Kemp (and design), Kendo UI, Kinvey, LoadMaster, MessageWay, MOVEit, NativeChat, OpenEdge, Powered by Chef, Powered by Progress, Progress, Progress Software Developers Network, SequeLink, Sitefinity (and Design), Sitefinity, Sitefinity (and design), Sitefinity Insight, SpeedScript, Stylized Design (Arrow/3D Box logo), Stylized Design (C Chef logo), Stylized Design of Samurai, TeamPulse, Telerik, Telerik (and design), Test Studio, WebSpeed, WhatsConfigured, WhatsConnected, WhatsUp, and WS_FTP are registered trademarks of Progress Software Corporation or one of its affiliates or subsidiaries in the U.S. and/or other countries.

Analytics360, AppServer, BusinessEdge, Chef Automate, Chef Compliance, Chef Desktop, Chef Workstation, Corticon Rules, Data Access, DataDirect Autonomous REST Connector, DataDirect Spy, DevCraft, Fiddler, Fiddler Classic, Fiddler Everywhere, Fiddler Jam, FiddlerCap, FiddlerCore, FiddlerScript, Hybrid Data Pipeline, iMail, InstaRelinker, JustAssembly, JustDecompile, JustMock, KendoReact, OpenAccess, PASOE, Pro2, ProDataSet, Progress Results, Progress Software, ProVision, PSE Pro, Push Jobs, SafeSpaceVR, Sitefinity Cloud, Sitefinity CMS, Sitefinity Digital Experience Cloud, Sitefinity Feather, Sitefinity Thunder, SmartBrowser, SmartComponent, SmartDataBrowser, SmartDataObjects, SmartDataView, SmartDialog, SmartFolder, SmartFrame, SmartObjects, SmartPanel, SmartQuery, SmartViewer, SmartWindow, Supermarket, SupportLink, Unite UX, and WebClient are trademarks or service marks of Progress Software Corporation and/or its subsidiaries or affiliates in the U.S. and other countries. Java is a registered trademark of Oracle and/or its affiliates. Any other marks contained herein may be trademarks of their respective owners.

Please refer to the NOTICE.txt or Release Notes – Third-Party Acknowledgements file applicable to a particular Progress product/hosted service offering release for any related required third-party acknowledgements.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

Table of Contents

1 Introduction **4**

2 Prerequisites **5**

3 Deploy a LoadMaster in the Open Telekom Cloud Platform **6**

4 Shutting Down the LoadMaster **10**

4.1 Shut Down using the OTC UI 10

4.2 Shut Down using the LoadMaster UI 11

5 High Availability (HA) Configuration **12**

5.1 Configure the LoadMasters 12

5.2 Create an Enhanced Load Balancer 13

6 Useful Links **18**

Last Updated Date **19**

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

1 Introduction

Open Telekom Cloud (OTC) is an international, large-scale, public OpenStack Powered Platform from Deutsche Telekom supported and operated by T-Systems out of Europe. It has been designed for simplicity, security, compliance, affordability, and openness.

OTC customers can now use the Kemp LoadMaster for enhanced load balancing that offers additional security features and advanced load balancing capabilities in an easily-managed solution. Compared to Elastic Load Balancing on OTC, the LoadMaster makes it easy to provide the best performance and security for your applications and simplifies operation with management using a web interface or using an Application Programming Interface (API).

The LoadMaster feature highlights are as follows:

- Web Application Firewall (WAF) to protect applications against attack
- Pre-authentication and Single Sign-On (SSO) of users
- Advanced health checking for better detection of server outages
- Content rules for intelligent traffic management and control
- Advanced session persistence and load balancing options including cookies
- Support for multiple digital certificates and Server Name Indication (SNI)
- Pre-defined application templates for quick setup
- Manage using a web interface or using an API

LoadMaster is an OTC-approved solution that delivers security, resilience and application availability to over 10,000 customers worldwide.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

2 Prerequisites

The following prerequisites must be configured before attempting the steps in this document:


- You must have an OTC account.
- The Kemp LoadMaster private image must be uploaded to the OTC workspace.
- You must have access to the relevant Virtual Private Clouds (VPCs) and subnets.
- A security group must be configured specifying the relevant ports and protocols. Kemp recommends having:
    - TCP rules for ports 8443, 6973 (for High Availability (HA) synchronization), and 8444
    - A UDP rule for port 53 (for DNS)
    - An SSH rule for port 22 (not essential unless it is a GEO LoadMaster or you are using Kemp 360 Central or Kemp 360 Vision)
- An External IP address (EIP) must be configured.
- For a single LoadMaster with a Public IP address (PIP), if you want more than one Virtual Service IP address then you need multiple PIPs. You cannot bind PIPs to Virtual Services (only Network Interface Cards (NICs)) so the LoadMaster needs multiple NICs.
- For High Availability (HA) LoadMasters with an Enhanced Load Balancer (ELB), the ELB must be configured to allow NAT from public or multiple PIPs to each Virtual Service.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.


3 Deploy a LoadMaster in the Open Telekom Cloud Platform

To deploy a LoadMaster in the Open Telekom Cloud platform, follow the steps below:


1. Log in to the relevant Open Telekom Cloud workspace.



2. Click **Elastic Cloud Server**.




3. Click **Create ECS**.




4. Select the relevant **Region**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.




5. Select the relevant specification.

> Ensure to select a configuration with a minimum of 2 vCPUs and 2 GB of memory.



6. Select **Private Image** and select the Kemp LoadMaster image you have previously uploaded.




7. Enter the disk size.


> 20 GB is the recommended disk size. There is no need to add an extra disk.

8. Click **Next: Configure Network** in the bottom-right.


© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.



9. Select the relevant VPC and specify the IP address details.




10. Select the relevant security groups.



11. Specify the relevant Elastic IP (EIP).
12. Click **Next: Configure Advanced Settings** in the bottom-right.



13. Specify an **ECS Name**.




14. Select the relevant **Key Pair** (or create a new key pair) and select the check box.
15. Click **Next: Confirm**.




16. Confirm the settings and click **Create Now**.


© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.



17. Wait for the LoadMaster to be created. This can take a couple of minutes.



18. The **Status** changes to **Running** when the LoadMaster is created successfully.



19. Access the LoadMaster using the EIP by entering **https://<EIP>:8443** in the address bar.

For details on licensing the LoadMaster, refer to the Licensing Feature Description document.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.


4 Shutting Down the LoadMaster

There are two ways to shut down the LoadMaster - using the OTC UI or the LoadMaster UI. Refer to the sections below for step-by-step instructions.

4.1 Shut Down using the OTC UI

To shut down using the OTC UI, follow these steps:

1. Log in to the relevant Open Telekom Cloud workspace.




2. Click **Elastic Cloud Server**.
3. Click the **Name/ID** of the LoadMaster to shut down.



4. Click **Stop**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.




5. Select the **Forcibly stop the preceding ECSs** check box.
6. Click **Yes**.

4.2 Shut Down using the LoadMaster UI

To shut down the LoadMaster using the LoadMaster UI, follow these steps:


1. Log in to the LoadMaster UI.
2. Go to **System Configuration > System Administration > System Reboot**.



3. Click **Shutdown**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

5 High Availability (HA) Configuration



To set up HA, you must first configure the LoadMasters and then create an Enhanced Load Balancer in Open Telekom Cloud and add both LoadMasters as backend servers. For further details, refer to the sections below.

5.1 Configure the LoadMasters

To set up a HA configuration, follow the steps below:

1. First, deploy and license both LoadMasters following the steps in the **Deploy a LoadMaster in the Open Telekom Cloud Platform** section.
2. Access the LoadMaster using the EIP.
3. In the main menu, go to **System Configuration > OpenCloud HA Parameters**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

4. Select **First HA Mode** in the **OpenCloud HA Mode** drop-down list.

5. Select the desired option in the **Switch to Preferred Server** drop-down list:

   - **No Preferred Host:** Each unit takes over when the other unit fails. No switchover is performed when the partner is restarted.

   - **Prefer First:** The HA1 (active) unit always takes over. This is the default option.

6. Enter the internal address of the standby LoadMaster unit in the **Partner Name/IP** text box and click **Set Partner Name/IP**.

7. Enter **8444** as the **Health Check Port** and click **Set Health Check Port**.

   The **Health Check Port** must be set to **8444** on both the active and standby units for HA to function correctly.


8. If using a multi-arm configuration, select the **Health Check on All Interfaces** check box.

   If this option is disabled, the health check listens on the primary eth0 address.

9. Then, access the UI of the standby unit. Complete the same steps above in the standby unit but select **Second HA Mode** as the **OpenCloud HA Mode** instead.


5.2 Create an Enhanced Load Balancer

Now that the LoadMaster settings are configured, you must create an Enhanced Load Balancer in Open Telekom Cloud and add both LoadMasters as backend servers. To do this, access the Open Telekom Cloud workspace and follow the steps below.



1. Click **Elastic Load Balancing**.


© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.




2. Click **Create Enhanced Load Balancer**.



3. Select the appropriate **Region**.



4. Complete the relevant settings, for example, select the correct **VPC** and **Subnet**.



5. Select either a new or existing **EIP**.

6. If you selected **New EIP**, set the **EIP Type** to **Dynamic BGP** and set the **Bandwidth** to the required rate.




7. Set the **Name** to be used for the Enhanced Load Balancer.


8. Click **Create Now**.

9. Review the configuration details and click **Submit**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.




10. Click the Name of the **ELB** to configure it.



11. Select **Listeners**.

12. Click **Add Listener**.




13. Specify the **Frontend Protocol/Port**.

> Set up the listener to use the same protocol and port as the Virtual Service in the LoadMaster configuration.


14. Click **Next**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

15. Either create a new backend server group or use an existing one. If creating a new one, follow the steps below. If you are using an existing backend server group, skip to the following step: **Ensure Enable Health Check is enabled.**



16. Set a **Name** for the backend server group.
17. Select **HTTP** as the **Backend Protocol**.
18. Select the appropriate **Load Balancing Algorithm**.




19. Ensure **Enable Health Check** is enabled.
20. Ensure to specify **HTTP** as the **Protocol** and **8444** as the **Port**.
21. Click **Finish**.




22. Select **Backend Server Groups**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.



23. Select the relevant backend server group and click **Add**.



24. Select the relevant backend servers (LoadMasters) from the list. You can select multiple servers.

25. Click **Next**.

26. If you selected multiple servers, enter **80** in the **Batch Add Port** field.

27. Click **Finish**.

The servers are added and it will take a few minutes for the health check result to normalize.

> It is expected that the **Health Check Result** for the HA active LoadMaster will be **Normal** and the HA standby will be **Abnormal**.

After successfully following these steps, HA configuration is set up and you can confirm this by connecting to the Public IP (EIP) of the Enhanced Load Balancer using a browser **http://<EIPofEnhancedLoadBalancer>** and this should operate based on the **Load Balancing Algorithm** specified when following the steps above.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

6 Useful Links

For further help with Open Telekom Cloud, refer to the following links:

- First Steps - https://open-telekom-cloud.com/en/support/tutorials/first-steps-with-open-telekom-cloud
- Tutorials - https://open-telekom-cloud.com/en/support/tutorials
- Community - https://community.open-telekom-cloud.com/community/?id=community_home

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

Last Updated Date

This document was last updated on 27 July 2023.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.