



ESP Steering Groups

Technical Note

UPDATED: 27 July 2023

Copyright Notices

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

These materials and all Progress® software products are copyrighted and all rights are reserved by Progress Software Corporation. The information in these materials is subject to change without notice, and Progress Software Corporation assumes no responsibility for any errors that may appear therein. The references in these materials to specific platforms supported are subject to change.

#1 Load Balancer in Price/Performance, 360 Central, 360 Vision, Chef, Chef (and design), Chef Habitat, Chef Infra, Code Can (and design), Compliance at Velocity, Corticon, Corticon.js, DataDirect (and design), DataDirect Cloud, DataDirect Connect, DataDirect Connect64, DataDirect XML Converters, DataDirect XQuery, DataRPM, Defrag This, Deliver More Than Expected, DevReach (and design), Driving Network Visibility, Flowmon, Inspec, Ipswitch, iMacros, K (stylized), Kemp, Kemp (and design), Kendo UI, Kinvey, LoadMaster, MessageWay, MOVEit, NativeChat, OpenEdge, Powered by Chef, Powered by Progress, Progress, Progress Software Developers Network, SequeLink, Sitefinity (and Design), Sitefinity, Sitefinity (and design), Sitefinity Insight, SpeedScript, Stylized Design (Arrow/3D Box logo), Stylized Design (C Chef logo), Stylized Design of Samurai, TeamPulse, Telerik, Telerik (and design), Test Studio, WebSpeed, WhatsConfigured, WhatsConnected, WhatsUp, and WS_FTP are registered trademarks of Progress Software Corporation or one of its affiliates or subsidiaries in the U.S. and/or other countries.

Analytics360, AppServer, BusinessEdge, Chef Automate, Chef Compliance, Chef Desktop, Chef Workstation, Corticon Rules, Data Access, DataDirect Autonomous REST Connector, DataDirect Spy, DevCraft, Fiddler, Fiddler Classic, Fiddler Everywhere, Fiddler Jam, FiddlerCap, FiddlerCore, FiddlerScript, Hybrid Data Pipeline, iMail, InstaRelinker, JustAssembly, JustDecompile, JustMock, KendoReact, OpenAccess, PASOE, Pro2, ProDataSet, Progress Results, Progress Software, ProVision, PSE Pro, Push Jobs, SafeSpaceVR, Sitefinity Cloud, Sitefinity CMS, Sitefinity Digital Experience Cloud, Sitefinity Feather, Sitefinity Thunder, SmartBrowser, SmartComponent, SmartDataBrowser, SmartDataObjects, SmartDataView, SmartDialog, SmartFolder, SmartFrame, SmartObjects, SmartPanel, SmartQuery, SmartViewer, SmartWindow, Supermarket, SupportLink, Unite UX, and WebClient are trademarks or service marks of Progress Software Corporation and/or its subsidiaries or affiliates in the U.S. and other countries. Java is a registered trademark of Oracle and/or its affiliates. Any other marks contained herein may be trademarks of their respective owners.

Please refer to the NOTICE.txt or Release Notes – Third-Party Acknowledgements file applicable to a particular Progress product/hosted service offering release for any related required third-party acknowledgements.

Table of Contents

1 Introduction	4
1.1 Document Purpose	4
1.2 Intended Audience	4
1.3 Prerequisites	4
2 How ESP Steering Groups Work	6
3 Configure ESP Steering Groups in the LoadMaster	7
3.1 Set the ESP Steering Groups in the Virtual Service(s)	7
3.1.1 Notes about Permitted Groups and Steering Groups	9
3.2 Create the Content Rules	10
3.3 Assign the Content Rule(s) to the Real Server(s)	11
4 References	14
ESP, Feature Description	14
Last Updated Date	15

1 Introduction

The Kemp LoadMaster Edge Security Pack (ESP) has the ability of steering client traffic to individual Real Servers in a Virtual Service based on the Active Directory (AD) group membership of users initiating client traffic. An example scenario would be a Virtual Service which has four Real Servers. Two Real Servers could be configured to have a primary association with Active Directory Group 1 and two Real Servers could be configured to have a primary association with AD Group 2. When a user attempts to access the Virtual Service, their group membership will be verified and the information used to steer their request to the appropriate Real Servers. If the Real Servers selected based on group membership are not available, the default behavior is to fall back to the assigned scheduling method for the Virtual Service.

1.1 Document Purpose

The purpose of this document is to provide information and instructions on how to configure the LoadMaster to steer client traffic based on group membership. For more information on the ESP feature and options in general, refer to the [ESP, Feature Description](#).

1.2 Intended Audience

This document is intended for network and application administrators that are interested in finding out more about using ESP for steering client traffic based on AD group membership in the Kemp LoadMaster.

1.3 Prerequisites

Before configuring ESP steering groups in LoadMaster, it is assumed that the following prerequisites have been met:

- The relevant configuration has been made in the Active Directory, (i.e. setting up user groups and adding the relevant users to the relevant groups.)
- A determination has been made as to which groups will be used to steer traffic to which Real Servers.
- The relevant Virtual Service(s) and Real Server(s) have been created and configured as needed. For information on how to configure Virtual Services, and the various features available in the Kemp LoadMaster, refer to the Kemp Documentation page: <http://kemptechnologies.com/documentation/>.

1 Introduction

- An appropriate **Client Authentication Mode** is being used (steering groups are not available for **Basic Authentication** or **SAML** authentication).
- Kerberos Constrained Delegation (KCD) is not in use (steering groups do not work with KCD).

2 How ESP Steering Groups Work

A description of how the ESP steering groups work is provided below:

1. The names of the desired Active Directory groups to perform steering on are entered into the **Steering Groups** text box in the Virtual Service modify screen in the LoadMaster.
2. When steering groups are specified in a Virtual Service and a user logs in, the username is tested to check if it exists in any of the steering groups, starting from the left.
3. If there is a match, the index of the matching group is returned in a cookie to the client. The index of the steering group is determined based on the position of the steering group in the **Steering Groups** text box, (i.e. the first group in the list has an index of 1, the second has an index of 2 and so on.) If the user is in multiple groups, the index of the first group in which the user is found is returned.
4. Content rules should be created to match each of the steering groups and assigned to the relevant Real Servers. On subsequent logins, the index number is used steer the traffic to the relevant Real Server.

For step-by-step instructions on how to configure this, refer to the **Configure ESP Steering Groups in the LoadMaster** section.


3 Configure ESP Steering Groups in the LoadMaster

Follow the steps in the sections below to configure ESP steering groups in the LoadMaster.

3.1 Set the ESP Steering Groups in the Virtual Service(s)

To configure ESP steering groups, follow the steps below in the Kemp LoadMaster Web User Interface (WUI). ESP SSO Domain settings must already be configured on the LoadMaster for this to function properly. See the [ESP, Feature Description](#) for details on configuring SSO Domains

1. In the main menu, go to **Virtual Services > View/Modify Services**.

Status	Real Servers	Operation
 Up	10.154.201.2	Modify Delete

2. Click **Modify** on the relevant Virtual Service.
3. Expand the **ESP Options** section and check the **Enable ESP** check box.

3 Configure ESP Steering Groups in the LoadMaster

ESP Options

Enable ESP

ESP Logging

User Access:

Security:

Connection:

Client Authentication Mode

Form Based

SSO Domain

[No Domain Set]

Alternative SSO Domains

Available Domain(s)

None Available

Assigned Domain(s)

None Assigned

Set Alternative SSO Domains

Allowed Virtual Hosts

Set Allowed Virtual Hosts

Allowed Virtual Directories

Set Allowed Directories

Pre-Authorization Excluded Directories

Set Excluded Directories

Permitted Groups

Group1;Group2

Set Permitted Groups

Permitted Group SID(s)

Set Permitted Group SIDs

Include Nested Groups

Steering Groups

Set Steering Groups

SSO Image Set

Exchange

SSO Greeting Message

Set SSO Greeting Message

Logoff String

Set SSO Logoff String

Display Public/Private Option

Disable Password Form

Use Session or Permanent Cookies

Session Cookies Only

User Password Change URL

Set Password Change URL

Server Authentication Mode

None

4. Select the appropriate **Client Authentication Mode** (steering groups are not available when using **Basic Authentication** or **SAML** authentication).

5. Enter the Active Directory group names which contain members that are allowed to access the service in the **Permitted Groups** field and click the **Set Permitted Groups** button.

6. Enter the Active Directory group names that will be used for steering traffic in the **Steering Groups** field and click the **Set Steering Groups** button.

Use a semi-colon to separate multiple group names.

The steering group index number will correspond to the location of the group in this list. In the example above - Group1 has an index of 1 and Group2 has an index of 2.

Do not enter the same group name in both the **Permitted Groups** and **Steering Groups** fields. This causes a conflict. When you specify a steering group, it is assumed to behave like a permitted group, so you do not need to enter the same group in both the **Permitted Groups** and **Steering Groups** fields.

7. Enable or disable the **Include Nested Groups** option.

This field relates to the **Permitted Groups** setting. Enable this option to include nested groups in the authentication attempt. If this option is disabled, only users in the top-level group will be granted access. If this option is enabled, users in both the top-level and first sub-level group will be granted access.

8. Configure any other settings as needed.

3.1.1 Notes about Permitted Groups and Steering Groups

Some notes around the permitted groups and steering groups are below:

- The **Permitted Groups** and **Steering Groups** entered should correspond to groups configured in the Active Directory.
- The permitted groups are the groups that are allowed to access this Virtual Service. When set, if a user logs in to an application published by this Virtual Service, the user must be a member of at least one of the groups specified.
- The **Permitted Group SID(s)** (security identifiers) field is the equivalent of the **Permitted Groups** field. If specifying permitted groups, you can complete either the **Permitted Groups** field or the **Permitted Groups SID(s)** field. In the **Permitted Group SID(s)** field:
 - You can specify the Group SIDs that are allowed to access this Virtual Service. After you type the groups, click **Set Permitted Group SIDs**.
 - You can a list of group SIDs of up to 64 bytes and 2048 characters in length.
 - Each group is separated by a semi-colon. Spaces are used to separate bytes in certain group SIDs. Here is an example:
S-1-5-21-703902271-2531649136-2593404273-1606. SIDs can be found by using the **get-adgroup-Identity GroupName** command.
- The **Steering Groups** steer client traffic to subsets of Real Servers in a Virtual Service based on group membership.
- Multiple groups are supported per Virtual Service up to a maximum of 2048 characters in length.

3 Configure ESP Steering Groups in the LoadMaster

- Performance may be impacted if a large number of groups are entered on a single Virtual Service.
- The steering group(s) entered must also be specified as permitted groups.
- If steering groups are specified for a Virtual Service, the group membership is tested for each group in the list - starting from the left. If there is a match - the first matching group is the one that will be used to steer the traffic.
- Groups entered are validated using an LDAP query to Active Directory
- The group(s) specified must be valid groups in the Active Directory domain that is specified in the SSO domain associated with the Virtual Service. The SSO domain name in the LoadMaster must be set to the Active Directory name as opposed to the DNS name of the service. For example, if the SSO domain in the LoadMaster is set to webmail.example but this is not the actual Active Directory domain FQDN, it will not function. Instead, the SSO domain would need to be set to .example.com.
- Multiple groups should be separated by a semi-colon (;). A space will not separate the groups since some group names may contain a space, such as **Domain Users**.
- The following characters are not allowed in permitted group names:
/ : + *
- The authentication protocol of the SSO domain must be LDAP when using these groups.
- The groups should be specified by name, not by full distinguished name (for example, “testgroup” as opposed to “CN=testgroup,CN=Users,DC=kemptech,DC=com”)
- If the Virtual Service configuration is updated while a user has an open session, the request may not be steered as expected. You could flush the cache as a workaround, but this would clear the cache for all Virtual Service users meaning they are forcibly disconnected.
- Do not enter the same group name in both the **Permitted Groups** and **Steering Groups** fields. This causes a conflict. When you specify a steering group, it is assumed to behave like a permitted group, so you do not need to enter the same group in both the **Permitted Groups** and **Steering Groups** fields.

3.2 Create the Content Rules

When a user logs in, the index number of the first matching steering group is used to create a cookie. The index number of the steering groups correspond to the order of the groups in the **Steering Groups** field in the Virtual Service, (that is, the first group has an index of 1, the second has an index of 2 and so on.)

The cookie is called **X-Kemp-STEERING**. Content rules should be created and added to the relevant Real Server(s) in order to match the relevant steering group and steer the traffic appropriately. To create a content rule for this purpose, follow the steps below:

1. In the main menu of the LoadMaster WUI, go to **Rules & Checking > Content Rules**.
2. Click **Create New**.

3 Configure ESP Steering Groups in the LoadMaster

Create Rule

Rule Name	ADGroup1
Rule Type	Content Matching ▼
Match Type	Regular Expression ▼
Header Field	Cookie
Match String	X-KEMP-STEERING=1
Negation	<input type="checkbox"/>
Ignore Case	<input type="checkbox"/>
Include Host in URL	<input type="checkbox"/>
Include Query in URL	<input type="checkbox"/>
Fail On Match	<input type="checkbox"/>
Perform If Flag Set	[Unset] ▼
Set Flag If Matched	[None] ▼

3. Enter a recognizable **Rule Name**.
4. Ensure the **Rule Type** is set to **Content Matching**.
5. Ensure the **Match Type** is set to **Regular Expression**.
6. Enter **Cookie** as the **Header Field**.
7. Enter **X-Kemp-STEERING=<IndexOfSteeringGroup>**, for example **X-Kemp-STEERING=1** to match the first group in the Steering Groups list.
8. Click **Create Rule**.
9. Repeat these steps for any other steering groups, as needed.

3.3 Assign the Content Rule(s) to the Real Server(s)

After creating the content rules, the rules need to be assigned to the relevant Real Server(s) in order to steer the traffic to those Real Servers based on the steering group. To assign a content rule to a Real Server, follow the steps below:

1. In the main menu of the LoadMaster WUI, go to **Virtual Services > View/Modify Services**.

Status	Real Servers	Operation
● Up	10.154.201.2	Modify Delete

3 Configure ESP Steering Groups in the LoadMaster

2. Click **Modify**.
3. Expand the **Advanced Properties** section.

Advanced Properties

Content Switching

Disabled

HTTP Selection Rules

Show Selection Rules

HTTP Header Modifications

Show Header Rules

Response Body Modification

Show Body Modification Rules

Enable HTTP/2 Stack

☐

Enable Caching

☐

Enable Compression

☐

Detect Malicious Requests

☐

Add Header to Request

:

Set Header

Copy Header in Request

To Header

Set Headers

Add HTTP Headers

Legacy Operation(X-ClientSide)

▼

"Sorry" Server

Port

Set Server Address

Not Available Redirection Handling

Error Code:

▼

Redirect URL:

https://%h%s

Set Redirect URL

Default Gateway

Set Default Gateway

Service Specific Access Control

Access Control

4. Click **Enable** in the **Content Switching** section.
5. Expand the **Real Servers** section.

Rules	Status	Operation
None	Enabled	<div>Disable</div> <div>Modify</div> <div>Delete</div>

6. Click the **None** button in the **Rules** column for the relevant Real Server.
7. Select the relevant rule from the **Rule** drop-down list.
8. Click **Add**.

OperationName	Match Type	Options	Header	Pattern
ADGroup1	RegEx		Cookie	X-KEMP-STEERING=1

9. Repeat these steps to assign the other rules to the relevant Real Servers, as needed.

If a content rule which matches on a steering group with the index 1 has been assigned to a Real Server, users in the first steering group listed in the **Steering Groups** field will be directed to that

3 Configure ESP Steering Groups in the LoadMaster

Real Server - if it is available. If the Real Server is not available, the traffic distribution will default to the **Scheduling Method** selected for the Virtual Service.

4 References

Unless otherwise specified, the following documents can be found at _
<http://kemptechnologies.com/documentation>.

ESP, Feature Description

Last Updated Date

This document was last updated on 27 July 2023.