



Epicor

Deployment Guide

UPDATED: 27 July 2023

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

These materials and all Progress® software products are copyrighted and all rights are reserved by Progress Software Corporation. The information in these materials is subject to change without notice, and Progress Software Corporation assumes no responsibility for any errors that may appear therein. The references in these materials to specific platforms supported are subject to change.

#1 Load Balancer in Price/Performance, 360 Central, 360 Vision, Chef, Chef (and design), Chef Habitat, Chef Infra, Code Can (and design), Compliance at Velocity, Corticon, Corticon.js, DataDirect (and design), DataDirect Cloud, DataDirect Connect, DataDirect Connect64, DataDirect XML Converters, DataDirect XQuery, DataRPM, Defrag This, Deliver More Than Expected, DevReach (and design), Driving Network Visibility, Flowmon, Inspec, Ipswitch, iMacros, K (stylized), Kemp, Kemp (and design), Kendo UI, Kinvey, LoadMaster, MessageWay, MOVEit, NativeChat, OpenEdge, Powered by Chef, Powered by Progress, Progress, Progress Software Developers Network, SequeLink, Sitefinity (and Design), Sitefinity, Sitefinity (and design), Sitefinity Insight, SpeedScript, Stylized Design (Arrow/3D Box logo), Stylized Design (C Chef logo), Stylized Design of Samurai, TeamPulse, Telerik, Telerik (and design), Test Studio, WebSpeed, WhatsConfigured, WhatsConnected, WhatsUp, and WS_FTP are registered trademarks of Progress Software Corporation or one of its affiliates or subsidiaries in the U.S. and/or other countries.

Analytics360, AppServer, BusinessEdge, Chef Automate, Chef Compliance, Chef Desktop, Chef Workstation, Corticon Rules, Data Access, DataDirect Autonomous REST Connector, DataDirect Spy, DevCraft, Fiddler, Fiddler Classic, Fiddler Everywhere, Fiddler Jam, FiddlerCap, FiddlerCore, FiddlerScript, Hybrid Data Pipeline, iMail, InstaRelinker, JustAssembly, JustDecompile, JustMock, KendoReact, OpenAccess, PASOE, Pro2, ProDataSet, Progress Results, Progress Software, ProVision, PSE Pro, Push Jobs, SafeSpaceVR, Sitefinity Cloud, Sitefinity CMS, Sitefinity Digital Experience Cloud, Sitefinity Feather, Sitefinity Thunder, SmartBrowser, SmartComponent, SmartDataBrowser, SmartDataObjects, SmartDataView, SmartDialog, SmartFolder, SmartFrame, SmartObjects, SmartPanel, SmartQuery, SmartViewer, SmartWindow, Supermarket, SupportLink, Unite UX, and WebClient are trademarks or service marks of Progress Software Corporation and/or its subsidiaries or affiliates in the U.S. and other countries. Java is a registered trademark of Oracle and/or its affiliates. Any other marks contained herein may be trademarks of their respective owners.

Please refer to the NOTICE.txt or Release Notes – Third-Party Acknowledgements file applicable to a particular Progress product/hosted service offering release for any related required third-party acknowledgements.

Table of Contents

1 Introduction	4
1.1 Document Purpose	4
1.2 Intended Audience	4
2 Template	5
3 Enable Subnet Originating Requests Globally	6
4 Configure Epicor ERP 10 Virtual Services	8
4.1 Epicor ERP 10 HTTP	8
References	10
Last Updated Date	11

1 Introduction

ERP 10 has been built from the ground up to comprehensively respond to the resource planning needs of enterprises and provide the support organizations require to thrive in today's competitive global business landscape. Guided by the needs of today's organizations, Epicor ERP 10 streamlines the use of Enterprise Resource Planning (ERP) across multiple devices while providing greater deployment choices, reduced complexity, and remarkable ease-of-use.

Such a powerful tool requires reliable and powerful support. The Kemp LoadMaster delivers an exceptional, cost-effective and easy to use solution which, by employing Adaptive Load Balancing, balances requests across Epicor ERP 10.

When deployed as a pair, two LoadMasters give the security of High Availability (HA). HA allows two physical or virtual machines to become one logical device. Only one of these units is ever handling traffic at any particular moment. One unit is active and the other is a hot standby (passive). This provides redundancy and resiliency, meaning if one LoadMaster goes down for any reason, the hot standby can become active, therefore avoiding any downtime. For more information on HA please refer to the: [High Availability \(HA\), Feature Description](#).

1.1 Document Purpose

This document provides guidance on deploying Epicor ERP 10 with a Kemp LoadMaster. The Kemp Support Team is available to provide solutions for scenarios not explicitly defined.

The Kemp support site can be found at: <https://support.kemptechnologies.com>.

1.2 Intended Audience

This document is for anyone deploying Epicor ERP 10 with a Kemp LoadMaster.

2 Template

Kemp has developed a template containing our recommended settings for this workload. You can install this template to help create Virtual Services (VSs) because it automatically populates the settings. You can use the template to easily create the required VSs with the recommended settings. You can remove templates after use and this will not affect deployed services. If needed, you can make changes to any of the VS settings after using the template.

Download released templates from the following page: [LoadMaster Templates](#).

For more information and steps on how to import and use templates, refer to the [Virtual Services and Templates, Feature Description](#) on the Kemp Documentation page.

3 Enable Subnet Originating Requests Globally

It is best practice to enable the **Subnet Originating Requests** option globally.

In a one-armed setup (where the Virtual Service and Real Servers are on the same network/subnet) **Subnet Originating Requests** is usually not needed. However, enabling **Subnet Originating Requests** should not affect the routing in a one-armed setup.

In a two-armed setup where the Virtual Service is on network/subnet A, for example, and the Real Servers are on network B, **Subnet Originating Requests** should be enabled on LoadMasters with firmware version 7.1-16 and above.

When **Subnet Originating Requests** is enabled, the LoadMaster routes traffic so that the Real Server sees traffic arriving from the LoadMaster interface that is in that network/subnet.

When **Subnet Originating Requests** is enabled globally, it is automatically enabled on all Virtual Services. If the **Subnet Originating Requests** option is disabled globally, you can choose whether to enable **Subnet Originating Requests** on a per-Virtual Service basis.

To enable **Subnet Originating Requests** globally, follow the steps below:

1. In the main menu of the LoadMaster Web User Interface (WUI), go to **System Configuration > Miscellaneous Options > Network Options**.

3 Enable Subnet Originating Requests Globally

Enable Server NAT

☒

Connection Timeout (secs)

660

Set Time

(Valid values:0, 60-86400)

Enable Non-Local Real Servers

☐

Enable Alternate GW support

☐

Enable TCP Timestamps

☐

Enable TCP Keepalives

☒

Enable Reset on Close

☐

Subnet Originating Requests

☒

Enforce Strict IP Routing

☐

Handle non HTTP Uploads

☐

Enable Connection Timeout Diagnostics

☐

Enable SSL Renegotiation

☒

Size of SSL Diffie-Hellman Key Exchange

2048 Bits

▼

Use Default Route Only

☐

HTTP(S) Proxy

Set HTTP(S) Proxy

2. Select the **Subnet Originating Requests** check box.

4 Configure Epicor ERP 10 Virtual Services

4.1 Epicor ERP 10 HTTP

The following are the steps involved and the values required to configure Epicor ERP 10 HTTP Virtual Service:

1. In the main menu of the LoadMaster Web User Interface (WUI), go to **Virtual Services > Add New**.

Please Specify the Parameters for the Virtual Service.

Virtual Address	<input type="text" value="10.154.11.131"/>
Port	<input type="text" value="808"/>
Service Name (Optional)	<input type="text" value="Epicor ERP 10"/>
Use Template	<input type="text" value="Select a Template"/>
Protocol	<input type="text" value="tcp"/>

2. Enter a valid IP address in the **Virtual Address** text box.
3. Enter **808** in the **Port** text box.
4. Enter a recognizable **Service Name**, for example **Epicor ERP 10**.
5. Ensure **tcp** is selected as the **Protocol**.
6. Click **Add this Virtual Service**.
7. Configure the settings as recommended in the following table:

Section	Option	Value
Standard Options	Force L4	Disabled

Section	Option	Value
	Transparency	Disabled
	Server Initiating Protocols	Normal Protocols
	Persistence Options	Source IP Address
	Timeout	2 Hours
	Scheduling Method	least connection
Real Servers	Real Server Check Method	TCP Connection Only
	Checked Port	808

8. Add the Real Servers:

- Click the **Add New** button.
- Enter the IP address of the ERP 10 server.
- Enter **808** as the **Port**.

The **Forwarding method** and **Weight** values are set by default.
An administrator can change these.

- Click **Add this Real Server**. Click **OK** to the pop-up message.
- Repeat the steps above to add more Real Servers as needed, based on the environment.

References

Unless otherwise specified, the following documents can be found at: <http://kemptechnologies.com/documentation>.

Virtual Services and Templates, Feature Description.

High Availability (HA), Feature Description

Last Updated Date

This document was last updated on 27 July 2023.