



# Moodle

## Deployment Guide

UPDATED: 29 July 2023

**© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.**

These materials and all Progress® software products are copyrighted and all rights are reserved by Progress Software Corporation. The information in these materials is subject to change without notice, and Progress Software Corporation assumes no responsibility for any errors that may appear therein. The references in these materials to specific platforms supported are subject to change.

#1 Load Balancer in Price/Performance, 360 Central, 360 Vision, Chef, Chef (and design), Chef Habitat, Chef Infra, Code Can (and design), Compliance at Velocity, Corticon, Corticon.js, DataDirect (and design), DataDirect Cloud, DataDirect Connect, DataDirect Connect64, DataDirect XML Converters, DataDirect XQuery, DataRPM, Defrag This, Deliver More Than Expected, DevReach (and design), Driving Network Visibility, Flowmon, Inspec, Ipswitch, iMacros, K (stylized), Kemp, Kemp (and design), Kendo UI, Kinvey, LoadMaster, MessageWay, MOVEit, NativeChat, OpenEdge, Powered by Chef, Powered by Progress, Progress, Progress Software Developers Network, SequeLink, Sitefinity (and Design), Sitefinity, Sitefinity (and design), Sitefinity Insight, SpeedScript, Stylized Design (Arrow/3D Box logo), Stylized Design (C Chef logo), Stylized Design of Samurai, TeamPulse, Telerik, Telerik (and design), Test Studio, WebSpeed, WhatsConfigured, WhatsConnected, WhatsUp, and WS\_FTP are registered trademarks of Progress Software Corporation or one of its affiliates or subsidiaries in the U.S. and/or other countries.

Analytics360, AppServer, BusinessEdge, Chef Automate, Chef Compliance, Chef Desktop, Chef Workstation, Corticon Rules, Data Access, DataDirect Autonomous REST Connector, DataDirect Spy, DevCraft, Fiddler, Fiddler Classic, Fiddler Everywhere, Fiddler Jam, FiddlerCap, FiddlerCore, FiddlerScript, Hybrid Data Pipeline, iMail, InstaRelinker, JustAssembly, JustDecompile, JustMock, KendoReact, OpenAccess, PASOE, Pro2, ProDataSet, Progress Results, Progress Software, ProVision, PSE Pro, Push Jobs, SafeSpaceVR, Sitefinity Cloud, Sitefinity CMS, Sitefinity Digital Experience Cloud, Sitefinity Feather, Sitefinity Thunder, SmartBrowser, SmartComponent, SmartDataBrowser, SmartDataObjects, SmartDataView, SmartDialog, SmartFolder, SmartFrame, SmartObjects, SmartPanel, SmartQuery, SmartViewer, SmartWindow, Supermarket, SupportLink, Unite UX, and WebClient are trademarks or service marks of Progress Software Corporation and/or its subsidiaries or affiliates in the U.S. and other countries. Java is a registered trademark of Oracle and/or its affiliates. Any other marks contained herein may be trademarks of their respective owners.

Please refer to the NOTICE.txt or Release Notes – Third-Party Acknowledgements file applicable to a particular Progress product/hosted service offering release for any related required third-party acknowledgements.

# Table of Contents

---

|   |           |
|---|-----------|
| <b>1 Introduction</b>                           | <b>4</b>  |
| 1.1 Document Purpose                            | 4         |
| 1.2 Intended Audience                           | 4         |
| 1.3 Prerequisites                               | 4         |
| <b>2 Deployment Options</b>                     | <b>5</b>  |
| <b>3 Recommended Configuration</b>              | <b>6</b>  |
| <b>4 Moodle Template</b>                        | <b>8</b>  |
| <b>5 Configure the LoadMaster</b>               | <b>9</b>  |
| 5.1 Create a HTTP Virtual Service               | 9         |
| 5.2 Create a HTTPS Virtual Service              | 10        |
| 5.3 Other Virtual Service Configuration Options | 12        |
| 5.3.1 Transparency and Non-Transparency         | 12        |
| 5.3.2 Session Persistence                       | 13        |
| 5.4 Moodle Server Configuration                 | 13        |
| 5.4.1 Routing                                   | 13        |
| 5.4.2 Moodle SSL Configuration                  | 13        |
| <b>Last Updated Date</b>                        | <b>15</b> |

# 1 Introduction

Moodle is a free open-source software e-learning platform. It is designed to provide educators, administrators and learners with a single robust, secure and integrated system to create personalized learning environments.

Moodle is designed to scale and can accommodate extremely large user communities. The Kemp LoadMaster makes scaling Moodle simpler by load balancing user traffic and offloading the security overhead.

## 1.1 Document Purpose

This document provides steps on how to configure the Kemp LoadMaster to load balance the Moodle platform. This document does not address the deployment of Moodle clusters and assumes a working knowledge of Moodle configuration editing and some basic LoadMaster skills. For further information on LoadMaster configuration in general, refer to the **Documentation** on the Kemp Support site: <https://support.kemptechnologies.com>.

## 1.2 Intended Audience

This document is intended to be read by anyone who is interested in learning about how to load balance the Moodle platform using a Kemp LoadMaster.

## 1.3 Prerequisites

There are some requirements that must be met before configuring the LoadMaster to load balance Moodle:

- The Moodle server(s) must be set up and configured correctly. For more information, please refer to the Moodle documentation.
- The Active Directory server must be set up and configured correctly. For more information, please refer to the Microsoft documentation.


# 2 Deployment Options

A number of options are available to deploy a load balancer in a Moodle environment. These are described below:

- **SSL offload and load balancing:** The LoadMaster terminates the SSL session and communicates with the appropriate server over HTTP. This approach ensures that all content is SSL encrypted.
- **SSL re-encrypt and load balancing:** The LoadMaster decrypts incoming traffic and re-encrypts when forwarding balanced traffic to the Moodle servers.
- **Layer 4 SSL balancing:** The LoadMaster balances SSL encrypted traffic between the Moodle servers. All SSL processing is performed by the Moodle servers.
- **Load balancing (without SSL offload):** In some situations you may not want the LoadMaster to handle SSL offloading.

This document provides step-by-step instructions for the first and last options above. For further help on configuring the other methods, please contact Kemp Support.

# 3 Recommended Configuration



### 3 Recommended Configuration

A one-arm or two-arm topology can be set up. It is also possible to have a High Availability (HA) setup which will provide redundancy. For more information on HA and how to configure it, refer to the **High Availability (HA), Feature Description**.

# 4 Moodle Template

Kemp have developed a template containing our recommended settings for Moodle. This template can be installed on the LoadMaster and can be used when creating each of the Virtual Services. Using a template automatically populates the settings in the Virtual Services. This is quicker and easier than manually configuring each Virtual Service. If needed, changes can be made to any of the Virtual Service settings after using the template.

Released templates can be downloaded from the Kemp documentation page:

<http://kemptechnologies.com/documentation>.

If you create another Virtual Service using the same template, ensure to change the **Service Name** to a unique name.

For more information and steps on how to import and use templates, refer to the **Virtual Services and Templates, Feature Description**.

For steps on how to manually add and configure each of the Virtual Services, refer to the **Configure the LoadMaster** section.



# 5 Configure the LoadMaster

Either a HTTP or HTTPS service can be set up, depending on the requirements. Follow the instructions in the relevant section below to set up the relevant Virtual Service.

## 5.1 Create a HTTP Virtual Service

In the main menu of the LoadMaster Web User Interface (WUI), follow the steps below:

1. Select **Virtual Services**.
2. Click **Add New**.

Please Specify the Parameters for the Virtual Service.

|                         |  |
|-------------------------|--|
| Virtual Address         | <input type="text" value="10.11.0.31"/>        |
| Port                    | <input type="text" value="80"/>                |
| Service Name (Optional) | <input type="text" value="Moodle_HTTP"/>       |
| Use Template            | <input type="text" value="Select a Template"/> |
| Protocol                | <input type="text" value="tcp"/>               |

3. Enter a valid **Virtual Address**.
4. Enter **80** as the **Port**.
5. Enter a recognizable name, for example **HTTP\_Moodle**.
6. Click **Add this Virtual Service**.
7. Configure the settings as recommended in the following table:

| Section                    | Option       | Value  |
|----------------------------|--------------|--|
| <b>Advanced Properties</b> | Error Code   | 302 Found  |
|                            | Redirect URL | https://%h%s <a href="#">Click <b>Set Redirect URL</b></a> |
| <b>Standard Options</b>    | Transparency | Disabled   |

8. Add the Real Servers:

## 5 Configure the LoadMaster

- a) Expand the **Real Servers** section.
- b) Click **Add New**.
- c) Enter the IP address of the back-end servers in the **Real Server Address** text box.
- d) Enter **80** as the **Port**.
- e) Click **Add this Real Server**.
- f) Click **OK**.
- g) Repeat the last four steps to add the other Real Servers.

## 5.2 Create a HTTPS Virtual Service



With this option, all client traffic is encrypted using SSL with the SSL being terminated on the LoadMaster. The LoadMaster balances the unencrypted traffic between the Moodle servers and re-encrypts the server replies to the client.

In the main menu of the LoadMaster WUI, follow the steps below:

1. Select **Virtual Services**.
2. Select **Add New**.

## 5 Configure the LoadMaster

**Please Specify the Parameters for the Virtual Service.**

---

Virtual Address

Port

Service Name (Optional)

Use Template

Protocol

3. Enter a valid **Virtual Address**.
4. Enter **443** as the **Port**.
5. Enter a recognizable **Service Name**, such as **HTTPS\_Moodle**.
6. Click **Add this Virtual Service**.
7. Configure the settings as recommended in the following table:

| Section                 | Option           | Value  | Comment           |
|-------------------------|------------------|--|-------------------|
| <b>SSL Properties</b>   | SSL Acceleration | Enabled  | Click <b>OK</b> . |
|                         | Certificates     | Select the relevant certificate and click the right arrow to move it to the <b>Assigned Certificates</b> box.* |                   |
|                         |                  | Click <b>Set Certificates</b>  |                   |
| <b>Standard Options</b> | Persistence Mode | Super HTTP   |                   |
| <b>Real Servers</b>     | Checked Port     | 389  |                   |

\*The self-signed certificate should be replaced with a proper certificate/key pair before deployment into a production environment. A single certificate secures all communications regardless of the number of Moodle servers deployed.

If there are no certificates listed, one must be uploaded. For further information on certificates, including steps on how to import and generate one, refer to the **SSL Accelerated Services, Feature Description**.

8. Add the Real Servers.

- a) Click **Add New**.
- b) Enter the IP address of the Moodle server in the **Real Server Address** text box.
- c) Enter the IP address of the Moodle server in the **Real Server Address** text box.
- d) Enter **80** as the **Port**.
- e) Click **Add This Real Server**.
- f) Click **OK**.
- g) Repeat steps b to f to add other Real Servers as needed.

### 5.3 Other Virtual Service Configuration Options

There are other Virtual Service configuration options to consider, such as transparency and session persistence which are referred to in the sections below.

#### 5.3.1 Transparency and Non-Transparency

A LoadMaster can be deployed in transparent or non-transparent mode. Transparent mode provides detailed client IP address information in the logs but it requires more configuration than non-transparent mode. Non-transparent mode requires no changes on the Moodle servers, but the Moodle logs will show all traffic as coming from the LoadMaster. The table below outlines some differences between transparent and non-transparent mode.

| Transparent  | Non-Transparent  |
|--|--|
| The Moodle server sees the client IP address as the source of a HTTP request.  | The Moodle server sees all requests as coming from the LoadMaster.                     |
| <p>The Moodle server must route all responses to the client IP address using the LoadMaster. This requires a routing change on the Moodle Server to either:</p> <ul style="list-style-type: none"> <li>• Set the default route (gateway) to be the LoadMaster, or;</li> <li>• Create static routes for each client subnet</li> </ul> <p>In practice, setting the default route to be the LoadMaster is the easiest option.</p> | The Moodle server replies directly back to the LoadMaster without any routing changes. |
| The Moodle logs contain the source IP address of the client.   | The Moodle logs show all traffic as coming from the LoadMaster.                        |

## 5 Configure the LoadMaster

| ▼ Standard Options                    |   |
|---------------------------------------|---|
| Transparency                          | <input type="checkbox"/>                              |
| Subnet Originating Requests           | Enabled   |
| Extra Ports                           | <input type="text"/> <a href="#">Set Extra Ports</a>  |
| Persistence Options                   | Mode: <input type="text" value="Super HTTP"/> ▼       |
|                                       | Timeout: <input type="text" value="6 Minutes"/> ▼     |
| Scheduling Method                     | <input type="text" value="round robin"/> ▼            |
| Idle Connection Timeout (Default 660) | <input type="text"/> <a href="#">Set Idle Timeout</a> |
| Quality of Service                    | <input type="text" value="Normal-Service"/> ▼         |

Transparency can be enabled/disabled in the **Standard Options** section of the Virtual Service modify screen.

### 5.3.2 Session Persistence

Depending on the configuration of the Moodle cluster, it may be desirable for a user to be continually served from the same Moodle server. By default, the LoadMaster will not use any persistence mechanism and a client request may be serviced by any of the Moodle servers in the cluster. Setting the **Persistence Mode** to **Super HTTP** will ensure that a client is serviced by the same server until the timeout period is reached. When using persistence, the **Persistence Timeout** value must match the inactivity timeout set in Moodle.

## 5.4 Moodle Server Configuration

Please ensure you have a restorable backup of any configuration before making these changes.

### 5.4.1 Routing

If using transparent mode in the LoadMaster, each Moodle server needs a routing update to provide a route back to the client via the LoadMaster. This can be implemented as a default route that points to the LoadMaster IP address or routes for the client subnet(s).

If using non-transparent mode on the LoadMaster, no routing changes are required.

### 5.4.2 Moodle SSL Configuration

The Moodle environment needs to be configured to support SSL proxies and to ensure that all URLs are HTTPS rather than HTTP. This configuration is stored in **config.php** which is located in the **moodle/htdocs** directory. Two changes are required to this file, as follows:

1. Configure Moodle to not do any SSL processing because that is being performed by the LoadMaster.

**\$CFG->sslproxy = 1;**

2. Tell Moodle to rewrite all URLs with HTTPS (as this is not done in the LoadMaster in a Moodle configuration). The **config.php** file usually selects the reply protocol based on the client request protocol. Update the code to ensure that all replies are HTTPS.

3. Before:

```
if ($_SERVER['HTTPS'] == 'on') { $CFG->wwwroot = 'https://' . $_SERVER['HTTP_HOST'] . '/moodle';}  
else { $CFG->wwwroot = 'http://' . $_SERVER['HTTP_HOST'] . '/moodle';};
```

After:

```
if ($_SERVER['HTTPS'] == 'on') { $CFG->wwwroot = 'https://' . $_SERVER['HTTP_HOST'] . '/moodle';}  
else { $CFG->wwwroot = 'https://' . $_SERVER['HTTP_HOST'] . '/moodle';};
```

The only change in the code is to add an **s** to the end of **http** in the **else** part of the **if** statement. Changing the **http://** to **https://** ensures that all URLs are prefixed by the correct protocol.

#### References

Unless otherwise specified, the following documents can be found at <http://kemptechnologies.com/documentation>.

**High Availability (HA), Feature Description**

**SSL Accelerated Services, Feature Description**

**Virtual Services and Templates, Feature Description**

**Web User Interface (WUI), Configuration Guide**

# Last Updated Date

This document was last updated on 29 July 2023.