

Microsoft Print Server

Deployment Guide

UPDATED: 27 July 2023

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

These materials and all Progress® software products are copyrighted and all rights are reserved by Progress Software Corporation. The information in these materials is subject to change without notice, and Progress Software Corporation assumes no responsibility for any errors that may appear therein. The references in these materials to specific platforms supported are subject to change.

#1 Load Balancer in Price/Performance, 360 Central, 360 Vision, Chef, Chef (and design), Chef Habitat, Chef Infra, Code Can (and design), Compliance at Velocity, Corticon, Corticon.js, DataDirect (and design), DataDirect Cloud, DataDirect Connect, DataDirect Connect64, DataDirect XML Converters, DataDirect XQuery, DataRPM, Defrag This, Deliver More Than Expected, DevReach (and design), Driving Network Visibility, Flowmon, Inspec, Ipswitch, iMacros, K (stylized), Kemp, Kemp (and design), Kendo UI, Kinvey, LoadMaster, MessageWay, MOVEit, NativeChat, OpenEdge, Powered by Chef, Powered by Progress, Progress, Progress Software Developers Network, SequeLink, Sitefinity (and Design), Sitefinity, Sitefinity (and design), Sitefinity Insight, SpeedScript, Stylized Design (Arrow/3D Box logo), Stylized Design (C Chef logo), Stylized Design of Samurai, TeamPulse, Telerik, Telerik (and design), Test Studio, WebSpeed, WhatsConfigured, WhatsConnected, WhatsUp, and WS_FTP are registered trademarks of Progress Software Corporation or one of its affiliates or subsidiaries in the U.S. and/or other countries.

Analytics360, AppServer, BusinessEdge, Chef Automate, Chef Compliance, Chef Desktop, Chef Workstation, Corticon Rules, Data Access, DataDirect Autonomous REST Connector, DataDirect Spy, DevCraft, Fiddler, Fiddler Classic, Fiddler Everywhere, Fiddler Jam, FiddlerCap, FiddlerCore, FiddlerScript, Hybrid Data Pipeline, iMail, InstaRelinker, JustAssembly, JustDecompile, JustMock, KendoReact, OpenAccess, PASOE, Pro2, ProDataSet, Progress Results, Progress Software, ProVision, PSE Pro, Push Jobs, SafeSpaceVR, Sitefinity Cloud, Sitefinity CMS, Sitefinity Digital Experience Cloud, Sitefinity Feather, Sitefinity Thunder, SmartBrowser, SmartComponent, SmartDataBrowser, SmartDataObjects, SmartDataView, SmartDialog, SmartFolder, SmartFrame, SmartObjects, SmartPanel, SmartQuery, SmartViewer, SmartWindow, Supermarket, SupportLink, Unite UX, and WebClient are trademarks or service marks of Progress Software Corporation and/or its subsidiaries or affiliates in the U.S. and other countries. Java is a registered trademark of Oracle and/or its affiliates. Any other marks contained herein may be trademarks of their respective owners.

Please refer to the NOTICE.txt or Release Notes – Third-Party Acknowledgements file applicable to a particular Progress product/hosted service offering release for any related required third-party acknowledgements.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

Table of Contents

1 Introduction **4**

1.1 Document Purpose 4

1.2 Intended Audience 4

2 Architecture **5**

3 Configure the LoadMaster **6**

3.1 Transparency Overview 6

3.2 Enable Check Persist Globally 6

4 Create a Microsoft Print Server Virtual Service **8**

Last Updated Date **10**

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

1 Introduction

Microsoft Print Server enables you to share printers throughout your organization from a single location.

The Kemp LoadMaster is used to load balance the Microsoft Print Server workload. The LoadMaster offers advanced Layer 4 and Layer 7 server load balancing, SSL Acceleration and a multitude of other advanced Application Delivery Controller (ADC) features. The LoadMaster intelligently and efficiently distributes user traffic among the application servers so that users get the best experience possible.

1.1 Document Purpose


This document provides the recommended LoadMaster settings used when load balancing the Microsoft Print Server workload. The Kemp Support Team is available to provide solutions for scenarios not explicitly defined. The Kemp support site can be found at: https://support.kemptechnologies.com

1.2 Intended Audience

This document is intended to be read by anyone who is interested in configuring the LoadMaster to optimize Microsoft Print Server.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

2 Architecture



© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

3 Configure the LoadMaster

The deployed Microsoft Print Server environment determines which of the following setups is used.

3.1 Transparency Overview

This service runs at Layer 4. All Layer 4 services are transparent. For transparency to work, the following rules/conditions must be met:

- The Real Server must have the LoadMaster as the default gateway
- The clients cannot be on the same subnet as the Real Server


For further details, refer to the **Transparency Requirements** section of the **Transparency Feature Description** on the Kemp Documentation Page.

3.2 Enable Check Persist Globally

It is recommended that you change the **Always Check Persist** option to **Yes – Accept Changes**. Use the following steps:

1. Go to **System Configuration > Miscellaneous Options > L7 Configuration**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.




2. Click the **Always Check Persist** dropdown arrow and select **Yes – Accept Changes**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

4 Create a Microsoft Print Server Virtual Service

The following are the steps involved and the recommended settings to configure the Microsoft Print Server Virtual Service:

1. In the main menu of the LoadMaster WUI, go to **Virtual Services > Add New**.



2. Type a valid **Virtual Address**.
3. Type ***** as the **Port**.
4. Type a recognizable **Service Name**, such as **Microsoft Print Server**.
5. Click **Add this Virtual Service**.
6. Configure the settings as recommended in the following table:

Section	Option	Value
Basic Properties	Service Type	Generic
Standard Options	Force L4	Enabled
	Persistence Options	Source IP Address
	Timeout	1 Hour
	Scheduling Method	least connection
Real Servers	Real Server Check Method	TCP Connection Only
	Checked Port	135

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

7. Add the Real Servers:

   a) Expand the **Real Servers** section.

   b) Click **Add New**.

   c) Enter the address of the relevant Real Server.

   d) Complete the other fields as required.

   e) Click **Add this Real Server** then click **OK** to the pop-up message.

   f) Repeat the steps above to add more Real Servers as needed, based on your environment.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

Last Updated Date

This document was last updated on 27 July 2023.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.