

Progress Sitefinity

Deployment Guide

UPDATED: 27 July 2023

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

These materials and all Progress® software products are copyrighted and all rights are reserved by Progress Software Corporation. The information in these materials is subject to change without notice, and Progress Software Corporation assumes no responsibility for any errors that may appear therein. The references in these materials to specific platforms supported are subject to change.

#1 Load Balancer in Price/Performance, 360 Central, 360 Vision, Chef, Chef (and design), Chef Habitat, Chef Infra, Code Can (and design), Compliance at Velocity, Corticon, Corticon.js, DataDirect (and design), DataDirect Cloud, DataDirect Connect, DataDirect Connect64, DataDirect XML Converters, DataDirect XQuery, DataRPM, Defrag This, Deliver More Than Expected, DevReach (and design), Driving Network Visibility, Flowmon, Inspec, Ipswitch, iMacros, K (stylized), Kemp, Kemp (and design), Kendo UI, Kinvey, LoadMaster, MessageWay, MOVEit, NativeChat, OpenEdge, Powered by Chef, Powered by Progress, Progress, Progress Software Developers Network, SequeLink, Sitefinity (and Design), Sitefinity, Sitefinity (and design), Sitefinity Insight, SpeedScript, Stylized Design (Arrow/3D Box logo), Stylized Design (C Chef logo), Stylized Design of Samurai, TeamPulse, Telerik, Telerik (and design), Test Studio, WebSpeed, WhatsConfigured, WhatsConnected, WhatsUp, and WS_FTP are registered trademarks of Progress Software Corporation or one of its affiliates or subsidiaries in the U.S. and/or other countries.

Analytics360, AppServer, BusinessEdge, Chef Automate, Chef Compliance, Chef Desktop, Chef Workstation, Corticon Rules, Data Access, DataDirect Autonomous REST Connector, DataDirect Spy, DevCraft, Fiddler, Fiddler Classic, Fiddler Everywhere, Fiddler Jam, FiddlerCap, FiddlerCore, FiddlerScript, Hybrid Data Pipeline, iMail, InstaRelinker, JustAssembly, JustDecompile, JustMock, KendoReact, OpenAccess, PASOE, Pro2, ProDataSet, Progress Results, Progress Software, ProVision, PSE Pro, Push Jobs, SafeSpaceVR, Sitefinity Cloud, Sitefinity CMS, Sitefinity Digital Experience Cloud, Sitefinity Feather, Sitefinity Thunder, SmartBrowser, SmartComponent, SmartDataBrowser, SmartDataObjects, SmartDataView, SmartDialog, SmartFolder, SmartFrame, SmartObjects, SmartPanel, SmartQuery, SmartViewer, SmartWindow, Supermarket, SupportLink, Unite UX, and WebClient are trademarks or service marks of Progress Software Corporation and/or its subsidiaries or affiliates in the U.S. and other countries. Java is a registered trademark of Oracle and/or its affiliates. Any other marks contained herein may be trademarks of their respective owners.

Please refer to the NOTICE.txt or Release Notes – Third-Party Acknowledgements file applicable to a particular Progress product/hosted service offering release for any related required third-party acknowledgements.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

Table of Contents

1 Introduction **4**

1.1 Document Purpose 4

1.2 Intended Audience 4

2 Template **5**

3 Architecture **6**

4 Configure the LoadMaster **7**

4.1 Enable Subnet Originating Requests Globally 7

5 Virtual Services **8**

5.1 Create the Sitefinity - HTTP Virtual Service 8

5.1.1 Sitefinity - HTTP Virtual Service Recommended API Settings (optional) 9

5.2 Create the Sitefinity – HTTPS Offloaded Virtual Services 9

5.2.1 Sitefinity – HTTPS Offloaded Virtual Service Recommended API Settings (optional) ...10

5.3 Create the Sitefinity – HTTPS Reencrypt Virtual Services 11

5.3.1 Sitefinity – HTTPS Reencrypt Virtual Service Recommended API Settings (optional) ...11

Last Updated Date **13**

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

1 Introduction

Progress Sitefinity® is an award-winning Web Content Management System empowering teams to independently create and manage content that delivers engaging digital experiences.

The LoadMaster delivers an exceptional, cost effective, and easy to use solution which by employing intelligent server health checking, load balancing, high availability, and security can support an always-on application experience for Sitefinity.

1.1 Document Purpose

This document provides the recommended LoadMaster settings used when providing load balancing for Sitefinity. The Kemp Support team is available to provide solutions for scenarios not explicitly defined. The Kemp Support site can be found at: https://support.kemptechnologies.com.

1.2 Intended Audience

This document is intended to be read by anyone who is interested in configuring the LoadMaster to optimize Sitefinity.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

2 Template

Kemp has developed a template containing our recommended settings for this workload. You can install this template to help create Virtual Services (VSs) because it automatically populates the settings. You can use the template to easily create the required VSs with the recommended settings. For some workloads, additional manual steps may be required such as assigning a certificate or applying port following. These steps are covered in the document, if needed.

You can remove templates after use and this will not affect deployed services. If needed, you can make changes to any of the VS settings after using the template.


Download released templates from the following page: LoadMaster Templates.

For more information and steps on how to import and use templates, refer to the Virtual Services and Templates, Feature Description on the Kemp Documentation page.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

3 Architecture

Progress Sitefinity deployments consist of multiple front-end servers running the Sitefinity CMS and a back-end SQL Server (SQL clustering recommended).



© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

4 Configure the LoadMaster

Refer to the sections below for details on some recommended global settings.

4.1 Enable Subnet Originating Requests Globally

It is best practice to enable the **Subnet Originating Requests** option globally.

In a one-armed setup (where the Virtual Service and Real Servers are on the same network/subnet) **Subnet Originating Requests** is usually not needed. However, enabling **Subnet Originating Requests** should not affect the routing in a one-armed setup.

In a two-armed setup where the Virtual Service is on network/subnet A, for example, and the Real Servers are on network B, **Subnet Originating Requests** should be enabled on LoadMasters with firmware version 7.1-16 and above.



When **Subnet Originating Requests** is enabled, the Real Server sees traffic originating from 10.20.20.21 (LoadMaster eth1 address) and responds correctly in most scenarios.

With **Subnet Originating Requests** disabled, the Real Server sees traffic originating from 10.0.0.15 (LoadMaster Virtual Service address on **eth0**) and responds to **eth0** which could cause asymmetric routing.

When **Subnet Originating Requests** is enabled globally, it is automatically enabled on all Virtual Services. If the **Subnet Originating Requests** option is disabled globally, you can choose whether to enable **Subnet Originating Requests** on a per-Virtual Service basis.

To enable **Subnet Originating Requests** globally, follow the steps below:

1. In the main menu of the LoadMaster User Interface (UI), go to **System Configuration > Miscellaneous Options > Network Options**.
2. Select the **Subnet Originating Requests** check box.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

5 Virtual Services


This step-by-step setup of Virtual Services (VSs) leverages the Kemp application template for Sitefinity. This template configures the Virtual Services to publish Sitefinity with HTTP, HTTPS with TLS/SSL Offloading, or HTTPS with TLS/SSL Reencryption.

The table in each section outlines the settings configured by the application template. You can use this information to manually configure Virtual Services or use the Kemp LoadMaster Application Programming Interface (API) and automation tools.

5.1 Create the Sitefinity - HTTP Virtual Service

The following are the steps involved and the recommended settings to configure the Sitefinity HTTP Virtual Service.

1. In the main menu of the LoadMaster User Interface (UI), go to **Virtual Services > Add New**.



2. Type a valid **Virtual Address**.
3. Select the **Sitefinity - HTTP** template in the **Use Template** drop-down list.
4. Click **Add this Virtual Service**.
5. Expand the **Real Servers** section.
6. Click **Add New**.
7. Type the **Real Server Address**.
8. Click **Add This Real Server**.
9. Repeat these steps to add more Real Servers as needed.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

5.1.1 Sitefinity - HTTP Virtual Service Recommended API Settings (optional)


This table outlines the API parameters and values set using the Kemp application template. You can use these settings with scripts and automation tools.

API Parameter	API Value
port	80
prot	tcp
VStype	http
Schedule	lc
Persist	none
CheckType	http
CheckPort	80

5.2 Create the Sitefinity – HTTPS Offloaded Virtual Services

The following are the steps involved and the recommended settings to configure the Sitefinity HTTPS Offloaded Virtual Service.

1. In the main menu of the LoadMaster User Interface (UI), go to **Virtual Services > Add New**.



2. Type a valid **Virtual Address**.
3. Select the **Sitefinity – HTTPS Offloaded** template in the **Use Template** drop-down list.
4. Click **Add this Virtual Service**.
5. Click **Virtual Services** and **View/Modify Services**.
6. Click **Modify** on the **Sitefinity – HTTPS Offloaded** Virtual Services on port 443.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

7. Expand the **SSL Properties** section.
8. Select the certificate to use from **Available Certificates** and click the arrow (>) to move it to **Assigned Certificates**.
9. Expand the **Real Servers** section.
10. Click **Add New**.
11. Type the **Real Server Address**.
12. Click **Add This Real Server**.
13. Repeat these steps to add more Real Servers as needed.

5.2.1 Sitefinity – HTTPS Offloaded Virtual Service Recommended API Settings (optional)

This table outlines the API parameters and values set using the Kemp application template. You can use these settings with scripts and automation tools.


API Parameter	API Value
port	443
prot	tcp
VStype	http
SubnetOriginating	1
Forcel7	1
Schedule	lc
SSLAcceleration	1
TLSType	7
CipherSet	BestPractices
CheckType	http
CheckUseGet	1
CheckPort	80

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

5.3 Create the Sitefinity – HTTPS Reencrypt Virtual Services

The following are the steps involved and the recommended settings to configure the Sitefinity HTTPS Reencrypt Virtual Service.

1. In the main menu of the LoadMaster User Interface (UI), go to **Virtual Services > Add New.**



2. Type a valid **Virtual Address**.
3. Select the **Sitefinity – HTTPS Reencrypt** template in the **Use Template** drop-down list.
4. Click **Add this Virtual Service**.
5. Click **Virtual Services** and **View/Modify Services**.
6. Click **Modify** on the **Sitefinity – HTTPS Reencrypt** Virtual Services on port 443.
7. Expand the **SSL Properties** section.
8. Select the certificate to use from **Available Certificates** and click the arrow (>) to move it to **Assigned Certificates**.
9. Expand the **Real Servers** section.
10. Click **Add New**.
11. Type the **Real Server Address**.
12. Click **Add This Real Server**.
13. Repeat these steps to add more Real Servers as needed.

5.3.1 Sitefinity – HTTPS Reencrypt Virtual Service Recommended API Settings (optional)

This table outlines the API parameters and values set using the Kemp application template. You can use these settings with scripts and automation tools.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

API Parameter	API Value
port	443
prot	tcp
VStype	http
SubnetOriginating	1
Forcel7	1
Schedule	lc
SSLAcceleration	1
Reencrypt	1
TLSType	7
CipherSet	BestPractices
CheckType	https
CheckUseGet	1
CheckPort	443

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

Last Updated Date

This document was last updated on 27 July 2023.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.