

WhatsUp Gold

Deployment Guide

UPDATED: 27 July 2023

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

These materials and all Progress® software products are copyrighted and all rights are reserved by Progress Software Corporation. The information in these materials is subject to change without notice, and Progress Software Corporation assumes no responsibility for any errors that may appear therein. The references in these materials to specific platforms supported are subject to change.

#1 Load Balancer in Price/Performance, 360 Central, 360 Vision, Chef, Chef (and design), Chef Habitat, Chef Infra, Code Can (and design), Compliance at Velocity, Corticon, Corticon.js, DataDirect (and design), DataDirect Cloud, DataDirect Connect, DataDirect Connect64, DataDirect XML Converters, DataDirect XQuery, DataRPM, Defrag This, Deliver More Than Expected, DevReach (and design), Driving Network Visibility, Flowmon, Inspec, Ipswitch, iMacros, K (stylized), Kemp, Kemp (and design), Kendo UI, Kinvey, LoadMaster, MessageWay, MOVEit, NativeChat, OpenEdge, Powered by Chef, Powered by Progress, Progress, Progress Software Developers Network, SequeLink, Sitefinity (and Design), Sitefinity, Sitefinity (and design), Sitefinity Insight, SpeedScript, Stylized Design (Arrow/3D Box logo), Stylized Design (C Chef logo), Stylized Design of Samurai, TeamPulse, Telerik, Telerik (and design), Test Studio, WebSpeed, WhatsConfigured, WhatsConnected, WhatsUp, and WS_FTP are registered trademarks of Progress Software Corporation or one of its affiliates or subsidiaries in the U.S. and/or other countries.

Analytics360, AppServer, BusinessEdge, Chef Automate, Chef Compliance, Chef Desktop, Chef Workstation, Corticon Rules, Data Access, DataDirect Autonomous REST Connector, DataDirect Spy, DevCraft, Fiddler, Fiddler Classic, Fiddler Everywhere, Fiddler Jam, FiddlerCap, FiddlerCore, FiddlerScript, Hybrid Data Pipeline, iMail, InstaRelinker, JustAssembly, JustDecompile, JustMock, KendoReact, OpenAccess, PASOE, Pro2, ProDataSet, Progress Results, Progress Software, ProVision, PSE Pro, Push Jobs, SafeSpaceVR, Sitefinity Cloud, Sitefinity CMS, Sitefinity Digital Experience Cloud, Sitefinity Feather, Sitefinity Thunder, SmartBrowser, SmartComponent, SmartDataBrowser, SmartDataObjects, SmartDataView, SmartDialog, SmartFolder, SmartFrame, SmartObjects, SmartPanel, SmartQuery, SmartViewer, SmartWindow, Supermarket, SupportLink, Unite UX, and WebClient are trademarks or service marks of Progress Software Corporation and/or its subsidiaries or affiliates in the U.S. and other countries. Java is a registered trademark of Oracle and/or its affiliates. Any other marks contained herein may be trademarks of their respective owners.

Please refer to the NOTICE.txt or Release Notes – Third-Party Acknowledgements file applicable to a particular Progress product/hosted service offering release for any related required third-party acknowledgements.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

Table of Contents

1 Introduction **4**

1.1 Document Purpose 4

1.2 Intended Audience 4

2 Template **5**

3 Architecture **6**

4 Configure the LoadMaster **7**

4.1 Enable Subnet Originating Requests Globally 7

5 Virtual Services **8**

5.1 Create the WhatsUp Gold Web Interface Virtual Service 8

5.1.1 WhatsUp Gold Web Interface Virtual Service Recommended API Settings (optional) ... 9

5.2 Create the WhatsUp Gold SNMP Virtual Services 9

5.2.1 WhatsUp Gold SNMP Virtual Service Recommended API Settings (optional) 11

5.3 Create the WhatsUp Gold Syslog Virtual Services 11

5.3.1 WhatsUp Gold Syslog Virtual Service Recommended API Settings (optional) 12

5.4 Create the WhatsUp Gold Netflow Virtual Services 13

5.4.1 WhatsUp Gold Netflow Virtual Service Recommended API Settings (optional) 14

5.5 Create the WhatsUp Gold Agent Virtual Services 14

5.5.1 WhatsUp Gold Agent Virtual Service Recommended API Settings (optional) 15

Last Updated Date **16**

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

1 Introduction

Progress WhatsUp Gold provides the necessary monitoring of everything that is connected to the organization's network. With features such as device monitoring, application monitoring, Network Traffic Analysis, Log Management, and Configuration Management, administrators can finally take full control of all the entire infrastructure.

The LoadMaster delivers an exceptional, cost effective, and easy to use solution which, by employing intelligent server health checking and automatic failover, can support an always-on application experience for WhatsUp Gold.

1.1 Document Purpose

This document provides the recommended LoadMaster settings used when providing high availability, optimization and security for WhatsUp Gold. The Kemp Support team is available to provide solutions for scenarios not explicitly defined. The Kemp Support site can be found at: https://support.kemptechnologies.com.

1.2 Intended Audience

This document is intended to be read by anyone who is interested in configuring the LoadMaster to optimize WhatsUp Gold.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

2 Template

Kemp has developed a template containing our recommended settings for this workload. You can install this template to help create Virtual Services (VSs) because it automatically populates the settings. You can use the template to easily create the required VSs with the recommended settings. For some workloads, additional manual steps may be required such as assigning a certificate or applying port following. These steps are covered in the document, if needed.

You can remove templates after use and this will not affect deployed services. If needed, you can make changes to any of the VS settings after using the template.


Download released templates from the following page: LoadMaster Templates.

For more information and steps on how to import and use templates, refer to the Virtual Services and Templates, Feature Description on the Kemp Documentation page.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

3 Architecture

WhatsUp Gold failover deployments consist of 2 front end servers running the WhatsUp Gold application and a back-end SQL Server (SQL clustering recommended).



© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

4 Configure the LoadMaster

Refer to the sections below for details on some recommended global settings.

4.1 Enable Subnet Originating Requests Globally

It is best practice to enable the **Subnet Originating Requests** option globally.

In a one-armed setup (where the Virtual Service and Real Servers are on the same network/subnet) **Subnet Originating Requests** is usually not needed. However, enabling **Subnet Originating Requests** should not affect the routing in a one-armed setup.

In a two-armed setup where the Virtual Service is on network/subnet A, for example, and the Real Servers are on network B, **Subnet Originating Requests** should be enabled on LoadMasters with firmware version 7.1-16 and above.



When **Subnet Originating Requests** is enabled, the Real Server sees traffic originating from 10.20.20.21 (LoadMaster eth1 address) and responds correctly in most scenarios.

With **Subnet Originating Requests** disabled, the Real Server sees traffic originating from 10.0.0.15 (LoadMaster Virtual Service address on **eth0**) and responds to **eth0** which could cause asymmetric routing.

When **Subnet Originating Requests** is enabled globally, it is automatically enabled on all Virtual Services. If the **Subnet Originating Requests** option is disabled globally, you can choose whether to enable **Subnet Originating Requests** on a per-Virtual Service basis.

To enable **Subnet Originating Requests** globally, follow the steps below:

1. In the main menu of the LoadMaster User Interface (UI), go to **System Configuration > Miscellaneous Options > Network Options**.
2. Select the **Subnet Originating Requests** check box.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

5 Virtual Services

WhatsUp Gold consists of several components that can failover automatically in the event of the primary server going offline. WhatsUp Gold Web Server interface is the primary Virtual Service that will be used for health checking to ensure the server is online and ready to accept traffic.


This step-by-step setup of Virtual Services (VSs) leverages the Kemp application template for WhatsUp Gold. This template configures the Virtual Services to leverage Layer 7 and transparency for the UDP services such as SNMP, Syslog, and Netflow. This approach will allow the real servers to see the source IP address of the devices running in the infrastructure.

The table in each section outlines the settings configured by the application template. You can use this information to manually configure Virtual Services or use the Kemp LoadMaster Application Programming Interface (API) and automation tools.

5.1 Create the WhatsUp Gold Web Interface Virtual Service

The following are the steps involved and the recommended settings to configure the WhatsUp Gold Web Interface.

1. In the main menu of the LoadMaster User Interface (UI), go to **Virtual Services > Add New**.



2. Type a valid **Virtual Address**.
3. Select the **WhatsUp Gold Web Interface** template in the **Use Template** drop-down list.
4. Click **Add this Virtual Service**.
5. Expand the **Real Servers** section.
6. Click **Add New**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

7. Type the **Real Server Address** of the primary WhatsUp Gold Server.
8. Keep the **Weight** at **1000** for the primary WhatsUp Gold Server.
9. Click **Add This Real Server**.
10. Click **Add New** for the standby WhatsUp Gold Server.
11. Set the **Weight** for the secondary WhatsUp Gold Server to **1**.
12. Click **Add This Real Server**.

5.1.1 WhatsUp Gold Web Interface Virtual Service Recommended API Settings (optional)

This table outlines the API parameters and values set using the Kemp application template. You can use these settings with scripts and automation tools.

API Parameter	API Value
port	443
prot	tcp
VStype	http
Schedule	fw
Persist	none
CheckType	tcp
CheckPort	9711


5.2 Create the WhatsUp Gold SNMP Virtual Services

The following are the steps involved and the recommended settings to configure the WhatsUp Gold SNMP Virtual Service:


> This Virtual Service requires the WhatsUp Gold Web Interface Virtual Service to be configured for the enhanced health checking feature.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

1. In the main menu of the LoadMaster User Interface (UI), go to **Virtual Services > Add New**.



2. Type a valid **Virtual Address**.
3. Select the **WhatsUp Gold SNMP** template in the **Use Template** drop-down list.
4. Click **Add this Virtual Service**.
5. Expand the **Real Servers** section.
6. Click **Add New**.
7. Type the **Real Server Address** of the primary WhatsUp Gold Server.
8. Keep the **Weight** at **1000** for the primary WhatsUp Gold Server.
9. Click **Add This Real Server**.
10. Click **Add New** for the standby WhatsUp Gold Server.
11. Set the **Weight** for the secondary WhatsUp Gold Server to **1**.
12. Click **Add This Real Server**.
13. Click **Back**.
14. Expand the **Real Servers** section.



15. For each Real Server select the same WhatsUp Gold Web Real Server IP Address with port 443 under **Healthcheck On**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

5.2.1 WhatsUp Gold SNMP Virtual Service Recommended API Settings (optional)

This table outlines the API parameters and values set using the Kemp application template. You can use these settings with scripts and automation tools.


API Parameter	API Value
port	162
prot	udp
Transparent	1
Schedule	fixed
EnhancedHealthchecks	1

5.3 Create the WhatsUp Gold Syslog Virtual Services

The following are the steps involved and the recommended settings to configure the WhatsUp Gold Syslog Virtual Service:

> This Virtual Service requires the WhatsUp Gold Web Interface Virtual Service to be configured for the enhanced health checking feature.


1. In the main menu of the LoadMaster User Interface (UI), go to **Virtual Services > Add New**.



2. Type a valid **Virtual Address**.
3. Select the **WhatsUp Gold Syslog** template in the **Use Template** drop-down list.
4. Click **Add this Virtual Service**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

5. Expand the **Real Servers** section.
6. Click **Add New**.
7. Type the **Real Server Address** of the primary WhatsUp Gold Server.
8. Keep the **Weight** at **1000** for the primary WhatsUp Gold Server.
9. Click **Add This Real Server**.
10. Click **Add New** for the standby WhatsUp Gold Server.
11. Set the **Weight** for the secondary WhatsUp Gold Server to **1**.
12. Click **Add This Real Server**.
13. Click **Back**.
14. Expand the **Real Servers** section.



15. For each Real Server select the same WhatsUp Gold Web Real Server IP Address with port 443 under **Healthcheck On**.

5.3.1 WhatsUp Gold Syslog Virtual Service Recommended API Settings (optional)

This table outlines the API parameters and values set using the Kemp application template. You can use these settings with scripts and automation tools.

API Parameter	API Value
port	514
prot	udp
Transparent	1
Schedule	fixed
EnhancedHealthchecks	1


© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

5.4 Create the WhatsUp Gold Netflow Virtual Services

The following are the steps involved and the recommended settings to configure the WhatsUp Gold Netflow Virtual Service:

> This Virtual Service requires the WhatsUp Gold Web Interface Virtual Service to be configured for the enhanced health checking feature.


1. In the main menu of the LoadMaster User Interface (UI), go to **Virtual Services > Add New**.



2. Type a valid **Virtual Address**.
3. Select the **WhatsUp Gold Netflow** template in the **Use Template** drop-down list.
4. Click **Add this Virtual Service**.
5. Expand the **Real Servers** section.
6. Click **Add New**.
7. Type the **Real Server Address** of the primary WhatsUp Gold Server.
8. Keep the **Weight** at **1000** for the primary WhatsUp Gold Server.
9. Click **Add This Real Server**.
10. Click **Add New** for the standby WhatsUp Gold Server.
11. Set the **Weight** for the secondary WhatsUp Gold Server to **1**.
12. Click **Add This Real Server**.
13. Click **Back**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

14. Expand the **Real Servers** section.



15. For each Real Server select the same WhatsUp Gold Web Real Server IP Address with port 443 under **Healthcheck On**.

5.4.1 WhatsUp Gold Netflow Virtual Service Recommended API Settings (optional)


This table outlines the API parameters and values set using the Kemp application template. You can use these settings with scripts and automation tools.

API Parameter	API Value
port	9999
prot	udp
Transparent	1
Schedule	fixed
EnhancedHealthchecks	1

5.5 Create the WhatsUp Gold Agent Virtual Services

The following are the steps involved and the recommended settings to configure the WhatsUp Gold Agent Virtual Service:

1. In the main menu of the LoadMaster User Interface (UI), go to **Virtual Services > Add New**.



2. Type a valid **Virtual Address**.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

3. Select the **WhatsUp Gold - Agent** template in the **Use Template** drop-down list.
4. Click **Add this Virtual Service**.
5. Expand the **Real Servers** section.
6. Click **Add New**.
7. Type the **Real Server Address** of the primary WhatsUp Gold Server.
8. Keep the **Weight** at **1000** for the primary WhatsUp Gold Server.
9. Click **Add This Real Server**.
10. Click **Add New** for the standby WhatsUp Gold Server.
11. Set the **Weight** for the secondary WhatsUp Gold Server to **1**.
12. Click **Add This Real Server**.

5.5.1 WhatsUp Gold Agent Virtual Service Recommended API Settings (optional)

This table outlines the API parameters and values set using the Kemp application template. You can use these settings with scripts and automation tools.

API Parameter	API Value
port	9749
prot	tcp
VStype	gen
Schedule	fw
Persist	none
CheckType	tcp
CheckPort	9711

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

Last Updated Date

This document was last updated on 27 July 2023.

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.