



OpenEdge Management: Alerts Guide and Reference

Progress® software products are copyrighted and all rights are reserved by Progress Software Corporation. This manual is also copyrighted and all rights are reserved. This manual may not, in whole or in part, be copied, photocopied, translated, or reduced to any electronic medium or machine-readable form without prior consent, in writing, from Progress Software Corporation. The information in this manual is subject to change without notice, and Progress Software Corporation assumes no responsibility for any errors that may appear in this document.

The references in this manual to specific platforms supported are subject to change.

A (and design), Actional, Actional (and design), Affinities Server, Allegrix, Allegrix (and design), Apama, Business Empowerment, ClientBuilder, ClientSoft, ClientSoft (and Design), Clientsoft.com, DataDirect (and design), DataDirect Connect, DataDirect Connect64, DataDirect Connect OLE DB, DataDirect Technologies, DataDirect XQuery, DataXtend, Dynamic Routing Architecture, EasyAsk, EdgeXtend, Empowerment Center, eXcelon, Fathom, IntelliStream, Neon, Neon New Era of Networks, O (and design), ObjectStore, OpenEdge, PDF, PeerDirect, Persistence, Persistence (and design), POSSENET, Powered by Progress, PowerTier, ProCare, Progress, Progress DataXtend, Progress Dynamics, Progress Business Empowerment, Progress Empowerment Center, Progress Empowerment Program, Progress Fast Track, Progress OpenEdge, Progress Profiles, Progress Results, Progress Software Developers Network, ProVision, PS Select, SequeLink, Shadow, ShadowDirect, Shadow Interface, Shadow Web Interface, ShadowWeb Server, Shadow TLS, SOAPStation, Sonic ESB, SonicMQ, Sonic Orchestration Server, Sonic Software (and design), SonicSynergy, SpeedScript, Stylus Studio, Technical Empowerment, Voice of Experience, WebSpeed, and Your Software, Our Technology—Experience the Connection are registered trademarks of Progress Software Corporation or one of its subsidiaries or affiliates in the U.S. and/or other countries. AccelEvent, Apama Dashboard Studio, Apama Event Manager, Apama Event Modeler, Apama Event Store, AppsAlive, AppServer, ASPen, ASP-in-a-Box, BusinessEdge, Cache-Forward, DataDirect Spy, DataDirect SupportLink, DataDirect XML Converters, Future Proof, Ghost Agents, GVAC, Looking Glass, ObjectCache, ObjectStore Inspector, ObjectStore Performance Expert, Pantero, POSSE, ProDataSet, Progress ESP Event Manager, Progress ESP Event Modeler, Progress Event Engine, Progress RFID, PSE Pro, SectorAlliance, SmartBrowser, SmartComponent, SmartDataBrowser, SmartDataObjects, SmartDataView, SmartDialog, SmartFolder, SmartFrame, SmartObjects, SmartPanel, SmartQuery, SmartViewer, SmartWindow, Sonic, Sonic Business Integration Suite, Sonic Process Manager, Sonic Collaboration Server, Sonic Continuous Availability Architecture, Sonic Database Service, Sonic Workbench, Sonic XML Server, The Brains Behind BAM, WebClient, and Who Makes Progress are trademarks or service marks of Progress Software Corporation or one of its subsidiaries or affiliates in the U.S. and other countries. Vermont Views is a registered trademark of Vermont Creative Software in the U.S. and other countries. IBM is a registered trademark of IBM Corporation. JMX and JMX-based marks and Java and all Java-based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries. Any other trademarks or service marks contained herein are the property of their respective owners.

OpenEdge Management Third Party Acknowledgements:

OpenEdge Management includes software developed by the Apache Software Foundation (<http://www.apache.org/>). Copyright © 1999 The Apache Software Foundation. All rights reserved (Xalan XSLT Processor), Copyright © 1999-2002 The Apache Software Foundation. All rights reserved (Xerces), Copyright © 1999-2000 The Apache Software Foundation. All rights reserved (Xerces), and Copyright © 2000-2002 The Apache Software Foundation. All rights reserved (Jakarta-Oro). The names “Apache,” “Xerces,” “Jakarta-Oro,” and “Apache Software Foundation” must not be used to endorse or promote products derived from this software without prior written permission. Products derived from this software may not be called “Apache” or “Jakarta-Oro,” nor may “Apache” or “Jakarta-Oro” appear in their name, without prior written permission of the Apache Software Foundation. For written permission, please contact apache@apache.org. Software distributed on an “AS IS” basis, WITHOUT WARRANTY OF ANY KIND, either express or implied. See the License for the specific language governing rights and limitations under the License agreement that accompanies the product.

OpenEdge Management includes software developed by Sun Microsystems, Inc. Copyright © 2003 Sun Microsystems, Inc. All Rights Reserved. Software distributed on an “AS IS” basis, WITHOUT WARRANTY OF ANY KIND, either express or implied. See the License for the specific language governing rights and limitations under the License agreement that accompanies the product.

OpenEdge Management includes software Copyright © 1994-2006 Sun Microsystems, Inc. All Rights Reserved. Software distributed on an “AS IS” basis, WITHOUT WARRANTY OF ANY KIND, either express or implied. See the License for the specific language governing rights and limitations under the License agreement that accompanies the product.

OpenEdge Management includes software Copyright 1994-2000 Sun Microsystems, Inc. All Rights Reserved. -Neither the name of or trademarks of Sun may be used to endorse or promote products including or derived from the Java Software technology without specific prior written permission; and Redistributions of source or binary code must contain the above copyright notice, this notice and the following disclaimers: This software is provided "AS IS," without a warranty of any kind. ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE HEREBY EXCLUDED. SUN MICROSYSTEMS, INC. AND ITS LICENSORS SHALL NOT BE LIABLE FOR ANY DAMAGES SUFFERED BY LICENSEE AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THE SOFTWARE OR ITS DERIVATIVES. IN NO EVENT WILL SUN MICROSYSTEMS, INC. OR ITS LICENSORS BE LIABLE FOR ANY LOST REVENUE, PROFIT OR DATA, OR FOR DIRECT, INDIRECT, SPECIAL, CONSEQUENTIAL, INCIDENTAL OR PUNITIVE DAMAGES, HOWEVER CAUSED AND REGARDLESS OF THE THEORY OF LIABILITY, ARISING OUT OF THE USE OF OR INABILITY TO USE SOFTWARE, EVEN IF SUN MICROSYSTEMS, INC. HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

OpenEdge Management includes Sonic and ObjectStore software which includes software developed by the ModelObjectsGroup (<http://www.modelobjects.com>). Copyright © 2000-2001 ModelObjects Group. All rights reserved. The name “ModelObjects” must not be used to endorse or promote products derived from the SSC Software without prior written permission. Products derived from the SSC Software may not be called “ModelObjects”, nor may “ModelObjects” appear in their name, without prior written permission. For written permission, please contact djacobson@modelobjects.com.

OpenEdge Management includes Sonic software which includes files that are subject to the Netscape Public License Version 1.1 (the “License”); you may not use this file except in compliance with the License. You may obtain a copy of the License at <http://www.mozilla.org/NPL>. Software distributed under the License is distributed on an “AS IS” basis, WITHOUT WARRANTY OF ANY KIND, either express or implied. See the License for the specific language governing rights and limitations under the License. The Original Code is Mozilla Communicator client code, released March 31, 1998. The Initial Developer of the Original Code is Netscape Communications Corporation. Portions created by Netscape are Copyright © 1998-1999 Netscape Communications Corporation. All Rights Reserved.

OpenEdge Management contains copyright material licensed from AdventNet, Inc. <http://www.adventnet.com>. All rights to such copyright material rest with AdventNet.

OpenEdge Management includes the RSA Data Security, Inc. MD5 Message-Digest Algorithm. Copyright © 1991-2, RSA Data Security, Inc. Created 1991. All rights reserved.

OpenEdge Management includes Sonic and ObjectStore software which include the JMX Technology from Sun Microsystems, Inc. Use and Distribution is subject to the Sun Community Source License available at <http://sun.com/software/communitysource>.

OpenEdge Management includes software Copyright © 2001-2003 James House. All rights reserved. Software distributed on an “AS IS” basis, WITHOUT WARRANTY OF ANY KIND, either express or implied. See the License for the specific language governing rights and limitations under the License agreement that accompanies the product. This product uses and includes within its distribution, software developed by the Apache Software Foundation (<http://www.apache.org/>).

OpenEdge Management includes code licensed from RSA Security, Inc. Some portions licensed from IBM are available at <http://oss.software.ibm.com/icu4j/>.

OpenEdge Management includes Sonic software, which includes code licensed from Mort Bay Consulting Pty. Ltd. The Jetty Package is Copyright © 1998 Mort Bay Consulting Pty. Ltd. (Australia) and others.



February 2008

Last updated with new content: Release 3.1B

Product Code: 4496; R3.1C

For the latest documentation updates see the [OpenEdge Product Documentation category](http://www.psdn.com/library/kbcategory.jspa?categoryID=129) on PSDN (<http://www.psdn.com/library/kbcategory.jspa?categoryID=129>).

Contents

Preface	Preface-1
1. Introduction	1-1
OpenEdge Management alert definition	1-2
How alerts relate to rules and actions	1-2
A cause and effect relationship	1-3
Using monitoring plans to set up rules-related criteria	1-3
Alert types	1-3
Polled alerts	1-4
Asynchronous alerts	1-6
Internal alerts	1-7
For additional alert information	1-8
2. Alerts Setup and Maintenance	2-1
Reviewing initial monitoring plan settings	2-2
Understanding alert options and default values	2-3
Configuring rules for individual resources	2-4
Setting threshold values	2-4
Configuration Advisor	2-5
Setting properties for generated alerts	2-5
Defining actions for alerts	2-10
Viewing alert information	2-10
The main menu bar	2-11
In the list frame	2-11
The detail frame	2-13
Views defined for collection pages	2-15
The Resource Monitoring Summary page	2-18
E-mail notifications	2-18
OpenEdge Management reports	2-19
The OpenEdge Management log file	2-20
The OpenEdge Management Trend Database	2-21
Clearing alerts through the management console	2-21
Clearing individual alerts	2-22
Clearing alerts in bulk	2-23

Disabling alerts	2-24
Disabling alerts in a monitoring plan	2-25
Disabling an individual resource monitor	2-27
Disabling alerts for all resources	2-28
Accessing alert information from the command-line interface	2-28
The OpenEdge Management environment window	2-29
Starting, querying, and stopping OpenEdge Management	2-29
Clearing an alert	2-30
Other alert commands	2-33
OpenEdge Management internal alerts	2-39
Defining an action for all internal alerts	2-39
Reviewing and processing internal alert data.	2-40
3. Alerts Reference	3-1
Alert organization and properties	3-2
Alert properties	3-2
<Specific Log File Rule Name>	3-3
ActionNotRun	3-3
AS_AverageProcedureDurationHigh	3-3
AS_BrokerAbnormalShutdown	3-4
AS_BrokerNormalShutdown	3-4
AS_BrokerStartup	3-4
AS_ClientAbnormalDisconnect	3-4
AS_NameServerUnavailable	3-4
AS_QueuedRequestPercentHigh	3-5
AS_RejectedRequestPercentHigh	3-5
AS_ServerAdded	3-5
AS_ServerKilled	3-6
AS_ServerTrimmed	3-6
AS_ServerUnavailable	3-6
BadSearchPattern	3-6
ContextSwitchHigh	3-7
CPUBusyThresholdExceeded	3-7
CPUNotFound	3-7
DB_AbnormalShutdown	3-8
DB_AgentCrash	3-8
DB_AgentDown	3-8
DB_AgentIdle	3-8
DB_AgentReadError	3-9
DB_AgentStartup	3-9
DB_AIWWWritePercentLow	3-9
DB_AreaSpaceUtilizationHigh	3-9
DB_AutoStartFail	3-10
DB_BIPartialWritesHigh	3-10
DB_BIWWWritePercentLow	3-10
DB_BrokerReconnectFail	3-10
DB_BufferIOHigh	3-11
DB_BuffersFlushedatCheckpointHigh	3-11
DB_BusyAIBufferWaitsHigh	3-11
DB_BusyBIBufferWaitsHigh	3-12
DB_CheckpointLengthShort	3-12
DB_DatabaseCommitsLow	3-12
DB_DatabaseCrash	3-12
DB_DatabaseDown	3-13
DB_EmptyAIBuffersWaitsHigh	3-13
DB_EmptyBIBufferWaitsHigh	3-13

DB_FathomTrendDatabase	3-13
DB_NormalShutdown	3-14
DB_PartialAIBufferWritesHigh	3-14
DB_PhysicalReadHigh	3-14
DB_ReadsToRequestsHigh	3-14
DB_RecordWaitsHigh	3-15
DB_ResourceAdded	3-15
DB_ResourceDisabled	3-15
DB_ResourceEnabled	3-15
DB_ResourceNameConflict	3-16
DB_Startup	3-16
DB_TrendingStopped	3-16
DB_UserCountHigh	3-16
DB_VariableAreaExtentGrow	3-17
DiminishedFileGrowth	3-17
DiskAvgQueueHigh	3-17
DiskBusyThresholdExceeded	3-18
DiskNotFound	3-18
ExcessiveFileGrowth	3-19
FathomTrendingUnavailable	3-19
FileDoesNotExist	3-19
FileExists	3-19
FilesDirectory	3-20
FileModified	3-20
FileSizeEqual	3-20
FileSizeExceeded	3-20
FileSizeLow	3-20
FileSizeNotEqual	3-21
FileStale	3-21
FileSystemNotFound	3-21
FileSystemUsedThresholdExceeded	3-22
HTTPDownloadFailure	3-22
HTTPRedirect	3-22
InvalidProgressVersion	3-23
JobStartFailure	3-23
LatchWaitCountHigh	3-23
LogActionWriteError	3-23
LogFileIOException	3-24
LogFileNotFound	3-24
MalformedPattern	3-24
MalformedURL	3-24
MemoryNotFound	3-25
NetworkResourceFailure	3-25
NetworkResourceTardy	3-25
NetworkResourceTimeout	3-25
NetworkResourceUnreachable	3-26
NoContentInPage	3-26
NoSearchCriteria	3-26
NS_AbnormalShutdown	3-26
NS_ApplicationServiceNotFound	3-27
NS_BrokerRegistrationFailure	3-27
NS_BrokerTimeout	3-27
NS_ClientRequestRejected	3-28
NS_DuplicateBrokerUUID	3-28
NS_NameServerReregisteredBroker	3-28
NS_NormalShutdown	3-28
NS_Startup	3-29

PageContentChanged	3-29
ProcessCPUBusyThresholdExceeded	3-29
ProcessPhysicalMemoryThresholdExceeded	3-29
ProcessVirtualMemoryThresholdExceeded	3-29
ProjectCreated	3-30
ProjectLoadFailed	3-30
ProjectNoRead	3-30
ProjectUpgraded	3-30
ProjectVersionLater	3-31
ReportRunFailed	3-31
ResrcDoesNotExist	3-33
RunQueueHigh	3-33
SearchPatternFound	3-34
SearchPatternNotFound	3-34
SystemMemoryUsedThresholdExceeded	3-34
TaskInQueueFailure	3-34
TaskExecFailure	3-34
TaskLocalDBAssocError	3-35
TaskQueueFull	3-35
TaskRemoteDBAssocError	3-35
TaskRunError	3-35
TaskStderrListenerFailed	3-35
TaskStdinReadFailed	3-36
TaskWaitFailure	3-36
TemplateNotLoaded	3-36
TimerExpired	3-36
VirtualMemoryUsedThresholdExceeded	3-37
WS_AgentAdded	3-37
WS_AgentKilled	3-37
WS_AgentTrimmed	3-37
WS_AgentUnavailable	3-38
WS_AverageProcedureDurationHigh	3-38
WS_BrokerAbnormalShutdown	3-38
WS_BrokerNormalShutdown	3-38
WS_BrokerStartup	3-38
WS_NameServerUnavailable	3-39
WS_QueuedRequestPercentHigh	3-39
WS_RejectedRequestPercentHigh	3-39

Index	Index-1
--------------------	----------------

Figures

Figure 1-1:	Sample polled alert-related data	1-5
Figure 1-2:	Sample asynchronous alert-related data	1-7
Figure 2-1:	Alerts default and override hierarchy	2-2
Figure 2-2:	Alert severity field and its four severity level options	2-6
Figure 2-3:	Number of alerts unseen total on the main menu bar	2-11
Figure 2-4:	Outstanding alerts displayed in the Alerts list frame	2-11
Figure 2-5:	ToolTip details displayed on the Alerts list frame	2-11
Figure 2-6:	ToolTip details displayed on the Resources list frame	2-12
Figure 2-7:	Alert details Summary page	2-13
Figure 2-8:	Resource with alerts viewlet	2-15
Figure 2-9:	Collection members viewlet sample	2-16
Figure 2-10:	A customized view of a My Collections page	2-16
Figure 2-11:	Alerts associated with a specific active resource monitor	2-18
Figure 2-12:	Expanded Reports categories	2-19
Figure 2-13:	Clear Alerts page	2-23
Figure 2-14:	Confirm Clearing Alerts page	2-24
Figure 2-15:	No open alerts message	2-24
Figure 2-16:	Set OpenEdge Management environment window	2-29
Figure 2-17:	-firealert command options	2-33
Figure 2-18:	Firing an alert	2-33
Figure 2-19:	-firealert command example	2-34
Figure 2-20:	-restype group selection option results	2-35
Figure 2-21:	-restype group option with verbose option results	2-36
Figure 2-22:	-alertlist in the command line	2-38
Figure 2-23:	-alertlist for openedge resource type	2-38
Figure 2-24:	-alertlist command used with -detail option	2-39
Figure 2-25:	-alertlist command used with -verbose option	2-39
Figure 2-26:	OpenEdge Management Internal Alerts page	2-40

Tables

Table 1–1: Accessing more information about alerts 1–8

Table 2–1: Additional monitoring plan and alerts information 2–4

Table 2–2: Alert details Summary page buttons 2–14

Table 2–3: Bulk Clear criteria options 2–23

Table 2–4: Options for starting and stopping OpenEdge Management 2–29

Table 2–5: Clear alert command options 2–30

Table 2–6: Alert list command group selection options 2–34

Table 2–7: Alert list command options to display additional details 2–36

Table 2–8: Alert list details 2–37

Preface

This Preface contains the following sections:

- [Purpose](#)
- [Audience](#)
- [Organization](#)
- [Using this manual](#)
- [Typographical conventions](#)
- [Examples of syntax descriptions](#)
- [OpenEdge messages](#)

Purpose

This combination guide and reference presents information to assist you in understanding and working with the OpenEdge® Management alert feature. Use this guide when performing any OpenEdge Management resource monitoring-related tasks.

Audience

This manual is designed for database administrators and end users of OpenEdge Management. This includes IT managers, ASP hosting companies, and others who are responsible for the day-to-day monitoring and management of resources, including databases and these OpenEdge® server products: AppServer™, WebSpeed® Transaction Server, and NameServer.

Organization

Chapter 1, “Introduction”

Introduces the OpenEdge Management alert feature, defines the alert types that can be generated, and identifies where you can find additional information about alerts in the OpenEdge Management documentation set.

Chapter 2, “Alerts Setup and Maintenance”

Provides detailed information about setting up, maintaining, and displaying alerts.

Chapter 3, “Alerts Reference”

Presents a comprehensive list of the OpenEdge-generated alerts and their associated polled or asynchronous property definitions.

Using this manual

OpenEdge provides a special purpose programming language for building business applications. In the documentation, the formal name for this language is *ABL (Advanced Business Language)*. With few exceptions, all keywords of the language appear in all UPPERCASE, using a font that is appropriate to the context. All other alphabetic language content appears in mixed case.

References to ABL compiler and run-time features

ABL is both a compiled and interpreted language that executes in a run-time engine that the documentation refers to as the *ABL Virtual Machine (AVM)*. When documentation refers to ABL source code compilation, it specifies *ABL* or *the compiler* as the actor that manages compile-time features of the language. When documentation refers to run-time behavior in an executing ABL program, it specifies *the AVM* as the actor that manages the specified run-time behavior in the program.

For example, these sentences refer to the ABL compiler's allowance for parameter passing and the AVM's possible response to that parameter passing at run time: "ABL allows you to pass a dynamic temp-table handle as a static temp-table parameter of a method. However, if at run time the passed dynamic temp-table schema does not match the schema of the static temp-table parameter, the AVM raises an error." The following sentence refers to run-time actions that the AVM can perform using a particular ABL feature: "The ABL socket object handle allows the AVM to connect with other ABL and non-ABL sessions using TCP/IP sockets."

References to ABL data types



ABL provides built-in data types, pre-defined class data types, and user-defined class data types. References to built-in data types follow these rules:

- Like most other keywords, references to specific built-in data types appear in all UPPERCASE, using a font that is appropriate to the context. No uppercase reference ever includes or implies any data type other than itself.
- Wherever *integer* appears, this is a reference to the INTEGER or INT64 data type.
- Wherever *decimal* appears, this is a reference to the DECIMAL data type.
- Wherever *numeric* appears, this is a reference to the INTEGER, INT64, or DECIMAL data type.

References to pre-defined class data types appear in mixed case with initial caps, for example, `Progress.Lang.Object`. References to user-defined class data types appear in mixed case, as specified for a given application example.

Typographical conventions

This manual uses the following typographical conventions:

Convention	Description
Bold	Bold typeface indicates commands or characters the user types, provides emphasis, or the names of user interface elements.
<i>Italic</i>	Italic typeface indicates the title of a document, or signifies new terms.
SMALL, BOLD CAPITAL LETTERS	Small, bold capital letters indicate OpenEdge key functions and generic keyboard keys; for example, GET and CTRL .
KEY1+KEY2	A plus sign between key names indicates a simultaneous key sequence: you press and hold down the first key while pressing the second key. For example, CTRL+X .
KEY1 KEY2	A space between key names indicates a sequential key sequence: you press and release the first key, then press another key. For example, ESCAPE H .
Syntax:	
Fixed width	A fixed-width font is used in syntax statements, code examples, system output, and filenames.
<i>Fixed-width italics</i>	Fixed-width italics indicate variables in syntax statements.
Fixed-width bold	Fixed-width bold indicates variables with special emphasis.
UPPERCASE fixed width	Uppercase words are ABL keywords. Although these are always shown in uppercase, you can type them in either uppercase or lowercase in a procedure.
	This icon (three arrows) introduces a multi-step procedure.
	This icon (one arrow) introduces a single-step procedure.
Period (.) or colon (:)	All statements except DO, FOR, FUNCTION, PROCEDURE, and REPEAT end with a period. DO, FOR, FUNCTION, PROCEDURE, and REPEAT statements can end with either a period or a colon.
[]	Large brackets indicate the items within them are optional.
[]	Small brackets are part of the ABL.
{ }	Large braces indicate the items within them are required. They are used to simplify complex syntax diagrams.
{ }	Small braces are part of the ABL. For example, a called external procedure must use braces when referencing arguments passed by a calling procedure.

Convention	Description
	A vertical bar indicates a choice.
...	Ellipses indicate repetition: you can choose one or more of the preceding items.

Examples of syntax descriptions

In this example, `ACCUM` is a keyword, and *aggregate* and *expression* are variables:

Syntax

```
ACCUM aggregate expression
```

`FOR` is one of the statements that can end with either a period or a colon, as in this example:

```
FOR EACH Customer:
  DISPLAY Name.
END.
```

In this example, `STREAM` *stream*, `UNLESS-HIDDEN`, and `NO-ERROR` are optional:

Syntax

```
DISPLAY [ STREAM stream ] [ UNLESS-HIDDEN ] [ NO-ERROR ]
```

In this example, the outer (small) brackets are part of the language, and the inner (large) brackets denote an optional item:

Syntax

```
INITIAL [ constant [ , constant ] ]
```

A called external procedure must use braces when referencing compile-time arguments passed by a calling procedure, as shown in this example:

Syntax

```
{ &argument-name }
```

In this example, `EACH`, `FIRST`, and `LAST` are optional, but you can choose only one of them:

Syntax

```
PRESELECT [ EACH | FIRST | LAST ] record-phrase
```

In this example, you must include two expressions, and optionally you can include more. Multiple expressions are separated by commas:

Syntax

```
MAXIMUM ( expression , expression [ , expression ] ... )
```

In this example, you must specify MESSAGE and at least one *expression* or SKIP [(*n*)], and any number of additional *expression* or SKIP [(*n*)] is allowed:

Syntax

```
MESSAGE { expression | SKIP [ ( n ) ] } ...
```

In this example, you must specify { *include-file*, then optionally any number of *argument* or &*argument-name* = "*argument-value*", and then terminate with }:

Syntax

```
{ include-file  
  [ argument | &argument-name = "argument-value" ] ... }
```

Long syntax descriptions split across lines

Some syntax descriptions are too long to fit on one line. When syntax descriptions are split across multiple lines, groups of optional and groups of required items are kept together in the required order.

In this example, WITH is followed by six optional items:

Syntax

```
WITH [ ACCUM max-length ] [ expression DOWN ]  
    [ CENTERED ] [ n COLUMNS ] [ SIDE-LABELS ]  
    [ STREAM-IO ]
```

Complex syntax descriptions with both required and optional elements

Some syntax descriptions are too complex to distinguish required and optional elements by bracketing only the optional elements. For such syntax, the descriptions include both braces (for required elements) and brackets (for optional elements).

In this example, ASSIGN requires either one or more *field* entries or one *record*. Options available with *field* or *record* are grouped with braces and brackets:

Syntax

```
ASSIGN  { [ FRAME frame ] { field [ = expression ] }
        [ WHEN expression ] } ...
      | { record [ EXCEPT field ... ] }
```

OpenEdge messages

OpenEdge displays several types of messages to inform you of routine and unusual occurrences:

- **Execution messages** inform you of errors encountered while OpenEdge is running a procedure; for example, if OpenEdge cannot find a record with a specified index field value.
- **Compile messages** inform you of errors found while OpenEdge is reading and analyzing a procedure before running it; for example, if a procedure references a table name that is not defined in the database.
- **Startup messages** inform you of unusual conditions detected while OpenEdge is getting ready to execute; for example, if you entered an invalid startup parameter.

After displaying a message, OpenEdge proceeds in one of several ways:

- Continues execution, subject to the error-processing actions that you specify or that are assumed as part of the procedure. This is the most common action taken after execution messages.
- Returns to the Procedure Editor, so you can correct an error in a procedure. This is the usual action taken after compiler messages.
- Halts processing of a procedure and returns immediately to the Procedure Editor. This does not happen often.
- Terminates the current session.

OpenEdge messages end with a message number in parentheses. In this example, the message number is 200:

```
** Unknown table name table. (200)
```

If you encounter an error that terminates OpenEdge, note the message number before restarting.

Obtaining more information about OpenEdge messages

In Windows platforms, use OpenEdge online help to obtain more information about OpenEdge messages. Many OpenEdge tools include the following Help menu options to provide information about messages:

- Choose **Help**→**Recent Messages** to display detailed descriptions of the most recent OpenEdge message and all other messages returned in the current session.
- Choose **Help**→**Messages** and then type the message number to display a description of a specific OpenEdge message.
- In the Procedure Editor, press the **HELP** key or **F1**.

On UNIX platforms, use the OpenEdge pro command to start a single-user mode character OpenEdge client session and view a brief description of a message by providing its number.



To use the pro command to obtain a message description by message number:

1. Start the Procedure Editor:

```
OpenEdge-install-dir/bin/pro
```

2. Press **F3** to access the menu bar, then choose **Help**→**Messages**.
3. Type the message number and press **ENTER**. Details about that message number appear.
4. Press **F4** to close the message, press **F3** to access the Procedure Editor menu, and choose **File**→**Exit**.

Introduction

This chapter introduces the OpenEdge® Management alert feature and identifies where you can find additional information about alerts in the OpenEdge Management documentation set, as outlined in the following sections:

- [OpenEdge Management alert definition](#)
- [How alerts relate to rules and actions](#)
- [Alert types](#)
- [For additional alert information](#)

OpenEdge Management alert definition

An *alert* is a notification that an event involving an OpenEdge Management resource has occurred. Alerts indicate that:

- A typical or routine event has occurred. For example, you can set up an alert to inform you that a database has started or stopped.
- A defined threshold has been met or exceeded. For example, you can set up an alert to be generated if the percentage of AppServer™ client requests rejected during a polling interval exceeds the defined threshold. The alert identifies a performance issue you might want to address.
- A situation has occurred with an internal OpenEdge Management operation. In this situation, OpenEdge Management automatically generates an alert. You cannot set up internal alerts.

When you configure resource monitoring, you define rules to ensure that a resource performs according to criteria you set. These rules cause OpenEdge Management to generate alerts if a specific condition occurs. Use alerts to ensure that:

- You are automatically notified if a rule is broken; all alert details display and are accessible through the management console.
- OpenEdge Management triggers optional, predefined corrective actions. You can customize and select actions, such as sending an e-mail to an employee, sending a voice message to a PDA (Personal Data Assistant), or initiating a job action or log file action in response to an event.

The prompt display of an alert and its associated details in the management console and the automatic and timely initiation of actions allow you to quickly recognize and correct resource-related violations.

How alerts relate to rules and actions

Alerts are triggered in response to rules that you associate with an OpenEdge Management resource or job. Each rule has its own unique alert and action definition. The content of this book focuses on alerts associated with resources. For details about setting up alerts for jobs and job instances, see the relevant section of the *OpenEdge Management: Resource Monitoring Guide*.

A cause and effect relationship

In OpenEdge Management, you can set up a simple, automated chain of events to ensure that you are notified of any resource rule violations. This sequence executes as follows:

1. Some condition causes a rule for an active resource to be violated.
2. The rule violation causes an alert to be triggered.
3. The alert causes a specific predefined action to occur.

Note: You define the action to be triggered by the alert. An alert can be triggered many times if a given condition exists, but the action that is associated with the alert will be run only when the alert is initially triggered. Once the alert is cleared, the alert and its related action can fire again.

Using monitoring plans to set up rules-related criteria

The values defined for each set of rule, alert, and action elements comprise a monitoring plan. A resource monitoring plan uses:

- A rule definition and its associated threshold values.
- An action that is initiated when the rule is violated.
- A schedule to identify when the rule is applied.
- A polling interval that determines how often the rule is evaluated.

Once a polling interval (that is, the time frequency with which OpenEdge Management monitors a resource) is set, OpenEdge Management recognizes the values you define for the monitoring plan attributes and executes them.

See the [“Example: Reviewing polled alert fields”](#) section on page 1–5 and the [“Example: Reviewing asynchronous alert fields”](#) section on page 1–7 for detailed information about setting up and maintaining alert-related details on monitoring plans.

Alert types

OpenEdge Management defines three types of alerts:

- Polled
- Asynchronous
- Internal

The rule definition determines what type of alert is associated with it.

Polled alerts

A *polled* alert is generated when the scheduled evaluation of a monitored resource detects an error or other condition in the resource. Polled alerts generally require threshold values to be defined so that OpenEdge Management can track a resource's performance in response to these parameters. For example, threshold values can include defining criteria such as a performance level that is lower or higher than a given number, or identifying the age of a file being older than a particular time (that is, minutes, hours, days, and so forth). Threshold values give you the flexibility to refine rule conditions based on the particular performance values you choose for a resource.

Factors associated with assessing threshold values

OpenEdge Management can trigger an alert when a monitored resource performs outside the currently defined value for a threshold rule. However, the defined polling interval could be set such that OpenEdge Management must complete x number of polling cycles (as defined in the **Throw alert after polled** field in the **Rule definition** section of a monitoring plan) before the alert is triggered.

For example, a CPU resource can be polled hourly to see if the CPU usage exceeds 90%. If the percentage does exceed 90%, an alert is generated. However, the alert will not trigger until the number of polling cycles as defined in the **Throw alert after polled** field is also exceeded.

Alerts that gather data through this polling process allow you to assess data polled over time to determine if your thresholds are too high or too low. You can adjust these threshold values, and the frequency with which the polling cycles are set to occur, at any time to refine your data collection.

The interpretation of a threshold value can vary from resource type to resource type. Differences in these interpretations can also affect what an alert display means for these various resource types. For an explanation of these resource-specific calculations, see the appropriate resource-specific rule details in the system, network, or file resource rule calculations in the *OpenEdge Management: Resource Monitoring Guide*. For details about database rule details, see the *OpenEdge Management: Database Management Guide*. For details about OpenEdge Management rules related to the OpenEdge server products, see the *OpenEdge Management: Servers Guide*.

Example: Reviewing polled alert fields

Figure 1–1 shows the **Create Monitoring Plan** page for a disk resource. In resource create mode, the **Rule definition** section contains the **Alert if disk activity exceeds** field, which is an example of a rule for which a polled alert is generated. The value defined for this threshold, and the values defined for the associated action and alert fields in this same section, enable OpenEdge Management to trigger a polled alert.

Create Monitoring Plan for: nbaspauldixp2.Disk-0_C

Save Cancel

Monitoring plan definition

Available Schedules: Default_Schedule

Polling Interval: 900 seconds

Alerts Enabled: ☒

Trend Performance Data: ☐

Trend Performance Data every: 1 poll(s)

Rule definition

Alert if disk activity exceeds: 90.0 %

Alert severity: Error

Throw alert after: 1 failed poll(s)

Always throw new alert: ☒

On alert perform action: Default_Action

Clear alert after: 0 successful poll(s)

On clear perform action: Default_Clear_Action

Progress Software Corporation (www.progress.com)

Figure 1–1: Sample polled alert-related data

The **Monitoring plan definition** section contains the **Polling Interval** field. Based on the value you define for this field, OpenEdge Management checks (polls) the resource according to the time interval specified. The default value of 900 seconds as shown in Figure 1–1 tells OpenEdge Management to check this disk resource every 15 minutes and keep a count of the number of passed or failed polls. OpenEdge Management also uses this count to assess the alert properties values defined in the **Rule definition** to determine when to throw or clear an alert. Note that the **Alerts Enabled** field is selected in Figure 1–1. OpenEdge Management will trigger alerts when the resource is active and a rule is violated.

The **Rule definition** section shows the rule-, alert-, and action-related fields for a disk resource monitor. Note that the rule definition is actually a combination of the threshold value and the specific action- and alert-related values that identify the activities OpenEdge Management performs if this threshold is exceeded.

As shown in the **Rules definition** section in [Figure 1–1](#), polled alerts require you to accept default values or set values in a combination of fields to establish the following criteria:

- The specific rule’s threshold which, when violated, causes an alert to trigger. In [Figure 1–1](#), the rule threshold is set at 90.0% in the **Alert if disk activity exceeds** field.
- The number of polls in which the condition must occur before an alert is generated. In [Figure 1–1](#), the **Throw alert after** field indicates that the alert will be generated after one failed poll.
- Whether to always throw a new alert. In [Figure 1–1](#), the option is selected.
- The number of polls in which the condition must occur without OpenEdge Management detecting any rule violations before the alert is automatically cleared. In [Figure 1–1](#), the value of **0** in the **Clear alert after** field indicates that the alert will not be automatically cleared. (If you choose not to clear an alert automatically, you must clear it manually.) See the “[Clearing alerts through the management console](#)” section on page 2–21 for more details about manually clearing alerts.
- The severity of the alert as defined in the **Alert severity** field: **Informational**, **Warning**, **Error**, or **Severe**.
- The action, if one is specified, to perform when the alert is generated.
- The action, if one is specified, to perform when the alert is cleared.

For more detailed information about defining alerts, see the “[Configuring rules for individual resources](#)” section on page 2–4.

Asynchronous alerts

An *asynchronous* alert is generated by a resource the moment a specific condition is detected, regardless of the polling interval set for that resource. Many asynchronous alerts identify violations related to mission-critical and time-sensitive activities. Others, such as **AS_BrokerNormalShutdown** or **DB_AgentStartup**, function as confirmations of normal, or expected, operational status.


Some common mission-critical conditions for which you can define an asynchronous alert include:

- Database abnormal shutdown.
- OpenEdge Management Trend Database Unavailable.
- AppServer added.

Other events for which you can define asynchronous alerts are more time-dependent. For example, if a running job has not completed in a specified period of time, you can be notified by an asynchronous alert. This situation could indicate that there is either a runaway or a hung job. In these types of instances, the firing of an asynchronous alert would inform you immediately of the situation so that you could take appropriate action.

Example: Reviewing asynchronous alert fields

Figure 1–2 shows a sample rule definition section of a resource monitoring plan. This sample shows both the alert severity and the action currently associated with a database agent abnormal shutdown condition.



Rule: Agent Abnormal Shutdown
Database: newLocalDB Schedule: Default Schedule

Save Cancel

Alert severity: Severe

On alert perform action: None

Always throw new alert: ☒

Rule description
The monitoring agent shutdown abnormally.

Figure 1–2: Sample asynchronous alert-related data

All asynchronous rules also have an **Always throw new alert** field. If you retain the default check mark in this field, OpenEdge Management triggers a new asynchronous alert of this type each time it detects that this rule is violated. Given the sample data shown in Figure 1–2, OpenEdge Management will trigger a unique alert each time a database agent shuts down in an abnormal manner. You can review each of these alert instances on the **Alert Detail Summary** page. If you clear the value in this field, OpenEdge Management triggers this alert once, so that an alert message does not display in the user interface each time the alert is triggered. However, even if you suppress this alert display, OpenEdge Management increments the **Occurrence count** field on the **Alert Detail Summary** page on a subsequent occurrence.

Internal alerts

OpenEdge Management internal alerts automatically inform you of events that occur internally to OpenEdge Management and for which you cannot set up specific alert definitions. For example, there is no option to define a rule, associated alert, and action for an internal event such as a CPU resource being unable to trend data to the OpenEdge Management Trend Database. In this instance, OpenEdge Management automatically triggers an alert.

Although OpenEdge Management automatically generates alerts for internal events, the alerts associated with internal situations appear on the management console and are processed in a manner similar to polled and asynchronous alerts. For more information about reviewing and processing alert data, see [Chapter 2, “Alerts Setup and Maintenance,”](#) and internal alert details in the [“OpenEdge Management internal alerts”](#) section on page 2–39.

For additional alert information

[Table 1–1](#) identifies where you can find additional information about OpenEdge Management alerts and alert-related topics.

Table 1–1: Accessing more information about alerts

For details about . . .	See . . .
Setting up, maintaining, and displaying alerts in OpenEdge Management.	Chapter 2, “Alerts Setup and Maintenance,” in this guide.
Any OpenEdge Management-generated alert and its associated polled or asynchronous property definition.	Chapter 3, “Alerts Reference,” in this guide.
All the basic elements of resource monitoring.	<i>OpenEdge Management: Resource Monitoring Guide</i>
Trending alert data to the OpenEdge Management Trend Database according to a database’s schema definition.	<i>OpenEdge Management: Trend Database Guide and Reference</i>
Creating and running OpenEdge Management-based reports that contain alert data.	<i>OpenEdge Management: Reporting Guide</i>

Alerts Setup and Maintenance

Key benefits of OpenEdge Management include its ability to generate alerts to notify appropriate personnel and invoke actions in response to conditions that occur on actively monitored resources.

This chapter contains these sections:

- [Reviewing initial monitoring plan settings](#)
- [Configuring rules for individual resources](#)
- [Viewing alert information](#)
- [Clearing alerts through the management console](#)
- [Disabling alerts](#)
- [Accessing alert information from the command-line interface](#)
- [OpenEdge Management internal alerts](#)

Reviewing initial monitoring plan settings

OpenEdge Management provides default options and values for various monitoring plan settings at the global, resource type, and individual resource monitor levels. You can change or override these options and values at any time. This section briefly reviews these initial monitoring plan settings, focusing specifically on the alert-specific options and default capabilities.

Figure 2–1 illustrates the alert default hierarchy and related options. The “[Understanding alert options and default values](#)” section on page 2–3 presents details about these options.




Figure 2–1: Alerts default and override hierarchy

Understanding alert options and default values

Figure 2–1 highlights some of the default values and the override hierarchy available when you set up resource monitoring plans. The primary purpose of the diagram is to focus on the alert-related options available at the global, resource type, and individual resource monitor levels.

General and Resource Monitoring options

The top block in Figure 2–1 identifies the options and defaults you can set globally on the **OpenEdge Management General Configuration** page and the **OpenEdge Management Resource Monitoring Configuration** page. You access these pages by choosing **Options**→**Configuration**.

Establishing alert-related options at this level can help to promote consistency within your alert data through the use of default values. However, you can override these default global settings at the resource type or individual resource monitor levels.

After you have defined your initial configuration settings, you can refine particular global settings by:

- Changing the alert-related selections.
- Turning global settings on or off. For example, you can elect to suspend OpenEdge Management’s alerts generation feature, or enable or disable resource polling for all active resource monitors.

Resource Monitor Defaults pages

The middle block in Figure 2–1 focuses on alert-related options available on the **Resource Monitor Defaults** pages. Among the various defaults values that you can set from each resource-specific default page, you can display and change default polling attributes associated with each resource type.

A polling interval determines how often a rule is evaluated. Therefore, you can determine a uniform polling interval that OpenEdge Management uses as a part of the criteria for determining when a rule violation will cause an alert to be triggered. Resource type default values can also be overridden at the individual resource monitor level.

Resource Monitoring Plan pages

The bottom block in Figure 2–1 identifies the lowest level in this hierarchy. This individual resource monitor level inherits values set at the higher global or resource type levels. When you override values on a **Resource Monitoring Plan** page for an individual resource monitor, your changes affect only the specific resource monitor.

For additional reference information

[Table 2–1](#) identifies where you can find additional details about monitoring plan- and alert-related functionality.

Table 2–1: Additional monitoring plan and alerts information

For details about . . .	See . . .
Selecting an action to be applied to all internal alerts.	The “ OpenEdge Management internal alerts ” section on page 2–39.
Accessing and changing values associated with resource monitor types.	The appropriate sections in the <i>OpenEdge Management: Resource Monitoring Guide</i> .
Accepting or overriding values at the individual resource level.	The “ Configuring rules for individual resources ” section on page 2–4.

Configuring rules for individual resources

This section identifies and describes the steps involved in configuring a rule, including:

- Setting threshold values.
- Setting properties, including a severity level, for generated alerts.
- Defining actions for alerts.

As described in the “[Reviewing initial monitoring plan settings](#)” section on page 2–2, default polling attributes automatically display at the individual resource level. You can change or override them to address your needs. The following sections explain what each of these activities involves.

Setting threshold values

Threshold values identify the rule component criteria of the polling attributes associated with a resource. These values typically identify the highest or lowest acceptable resource performance-related value for a specific resource. The type of threshold value varies according to the resource type. The OpenEdge Management System resource type threshold values are often characterized by the highest or lowest value definitions. The OpenEdge Management Network resource type threshold values relate to values defined for response times being greater than a specified value, or no response within a defined period of time.

During the monitoring process, when OpenEdge Management finds a value that is outside the defined threshold value, the rule is considered violated. This rule violation causes the alert to be generated and the action to trigger. See the “[How alerts relate to rules and actions](#)” section on page 1–2 for more information.

Knowing how OpenEdge Management interprets threshold values can help you to interpret more accurately the context of a specific alert. For an explanation of these resource-specific calculations, see the appropriate resource-specific rule details in the system, network, or file resource rule calculations in the *OpenEdge Management: Resource Monitoring Guide*. For details about database rule details, see the *OpenEdge Management: Database Management Guide*. For details about OpenEdge-related rules, see the *OpenEdge Management: Servers Guide*.

You can use threshold values supplied through these means:

- Default values.
- Values you type directly into the threshold fields in the **Rule definition** section.
- Values determined by the Configuration Advisor.

Configuration Advisor

The Configuration Advisor collects data about typical operating activities for specific resource rules for a time period that you set. Based on an analysis of this data, the Configuration Advisor suggests a range of threshold values from which you can select and then apply to a rule. The Configuration Advisor works with specific resource types.

See the *OpenEdge Management: Database Management Guide* for details about how the Configuration Advisor determines database resource-related recommended rule threshold settings. See the *OpenEdge Management: Servers Guide* for details about how the Configuration Advisor calculates WebSpeed® Transaction Server broker- and AppServer broker-related recommended rule threshold settings. See the *OpenEdge Management: Resource Monitoring Guide* for details about how the Configuration Advisor can be used to suggest rule thresholds for CPU, disk, and file system resources based on data in the OpenEdge Management Trend Database.

Setting properties for generated alerts

The alert-related properties are:

- **Alert severity**
- **Throw alert after**
- **Clear alert after**

The **Alert severity** property is set for all polled and asynchronous alerts. The **Throw alert after** property and the **Clear alert after** property provide mechanisms to reduce unnecessary noise in your polled alerts.

Assigning an alert's severity

You can assign an alert one of four severity levels. This allows you to choose which alerts are assigned highest priority based on the specific needs of your organization. The four levels of severity, from least to most severe, are:

- **Information**
- **Warning**
- **Error**
- **Severe**

To assign a severity to an alert, choose the desired severity from the **Alert severity** drop-down menu located in the **Rule definition** section of a monitoring plan page. Figure 2–2 shows the **Alert severity** field with the four severity levels displayed.

Rule: Average Procedure Duration High
Resource: asbroker1 Schedule: Default Schedule

Save Cancel

Defined Procedures
If you entered a procedure but did not Add/Update or Remove it, this procedure will be ignored when you save this page.

Procedure name	Threshold (in milliseconds)	Add/Update	Remove
<input type="text"/>	<input type="text"/>	<input type="button" value="Add/Update"/>	<input type="button" value="Remove"/>

Alert severity: **Warning** (dropdown menu open showing: Information, Warning, Error, Severe)

Throw alert after: poll(s)

Always throw new alert: ☐

On alert perform action: **Default_Action** (dropdown menu)

Clear alert after: successful poll(s)

On clear perform action: **None** (dropdown menu)

Rule description
The average time spent executing a procedure during the polling interval exceeded the threshold. Separate thresholds can be established for each procedure run (or to be run). This could indicate a bottleneck in the application or other unforeseen events inhibiting the offending procedure from executing as quickly as expected.

Progress Software Corporation (www.progress.com)

Figure 2–2: Alert severity field and its four severity level options

Specifying when to throw an alert

Noise is the normal variability that can occur while OpenEdge Management monitors a resource. For example, a CPU might run at 75% utilization with infrequent spikes of 100% utilization. The infrequent spikes are noise. You probably do not need to be alerted to those spikes because they do not reflect the true overall performance of the CPU. To avoid unnecessary alerts like these, you can set the **Throw alert after** and **Clear alert after** properties appropriately.

For example, you determine how many times a condition must occur before an alert is generated. Setting a low number, such as **1**, means you are more susceptible to noise. Setting this value to a higher number, such as **3**, reduces the likelihood of noise alerts, but also means an event must occur three times in a row before an alert is generated. The higher the setting of the **Throw alert after** property, the longer OpenEdge Management takes to generate an alert. For example, with a **Throw alert after** property set to **3**, three sample periods occur before the alert is generated.

Alert properties location in OpenEdge Management


Alert properties are located on the **Rule definition** section of a resource's **Monitoring Plan** page. Review and update the values associated with these alert properties as you edit monitoring plans for a resource.

The following procedure reviews the steps to edit a monitoring plan, noting the location and use of the alert properties.




To edit a resource monitoring plan:

1. In the **Resources** list, click the resource category that contains the resource you want to access. In this example, the category **System** is selected. Then select the specific default memory resource named **Memory** from the detail page. The **Monitoring Plan** page appears:



2. Click a schedule assigned to the monitoring plan. The **Schedule Monitoring Plan** page for Memory appears:



3. Click **Edit**. The **Resource Edit** page appears:

Edit Default_Schedule Monitoring Plan for: nbaspauldixp2.Memory

Save Cancel

Monitoring plan definition

Available Schedules: Default_Schedule

Polling Interval: 5 minutes

Alerts Enabled: ☒

Trend Performance Data: ☒

Trend Performance Data every: 1 poll(s)

Rule definition

Alert if system memory usage exceeds: 100.0 %

OR if virtual memory usage exceeds: 80.0 %

Alert severity: Error

Throw alert after: 2 failed poll(s)

Always throw new alert: ☐

On alert perform action: Default_Action

Clear alert after: 0 successful poll(s)

On clear perform action: None

Progress Software Corporation (www.progress.com)

The following table guides you in reviewing and updating values associated with the alert properties:

To change this alert property . . .	Perform this action . . .
Alert Severity	Select the drop-down list option to display the four severity options: Information , Warning , Error , and Severe .
Throw alert after	Enter the number of failed polls after which OpenEdge Management should trigger the alert. (For most resources, the default value is 1 . However, the default value for network resource monitors is 2 .) To minimize noise, consider setting this property to a low number for critical resources and to a higher number for less critical resources. Note: This property is not applicable to all resource monitors and does not appear on every resource property page.
Clear alert after	Enter one of the following three possible values to indicate when OpenEdge Management should clear an alert once the condition that prompted the alert has been resolved: <ul style="list-style-type: none"> • 0 — OpenEdge Management does not automatically clear an alert. You must manually clear the alerts. • 1 — OpenEdge Management automatically clears an alert the first time the resource successfully passes a poll. • A value greater than 1 — OpenEdge Management does not clear the alert until the resource passes this specified number of consecutive polls. This can prevent anti-noise from clearing an alert prematurely.

4. Click **Save**. Any changes you made to the alert properties will appear on the updated **Resource Monitoring plan** page for the Memory resource.

Defining actions for alerts

OpenEdge Management allows you to associate actions with each alert. Possible actions include:

- An e-mail notification. This action can be used to send e-mail to one or more operators. You can also send a message to electronic devices that support a text message display, such as a computer, PDA, pager, or cell phone.
- The running of a defined job. This action can be used to perform a recovery procedure to remedy the alert condition.
- An update to a log file.

For example, you can configure an e-mail action to send a message to the operator responsible for the resource on which an error occurred. You can also configure an alert to send e-mail to the responsible operator **and** execute a particular command at the same time. For detailed steps on creating actions and associating alerts with them, see the appropriate sections in the *OpenEdge Management: Resource Monitoring Guide*.

Viewing alert information

Details related to all outstanding alerts regardless of their type—polled, asynchronous, or internal—are visible through the management console. You can review alert data through various access points, such as:

- Reviewing alert totals information displayed next to the **Alerts** category on the main menu bar.
- Selecting **Alerts** on the main menu bar to display alert information in the list frame.
- Selecting **Alerts** on the main menu bar to display alert information in the detail frame.
- Reviewing summary alert information that can be displayed on views defined for collections pages.
- Reviewing alerts associated with a particular resource on the resource's monitoring summary page.
- Reviewing alert details that can be sent by e-mails to electronic mail boxes, PDAs, or other types of electronic devices that support text message displays.
- Generating and reviewing alert data using the OpenEdge Management reporting feature.
- Reviewing alert-related data in the AdminServer log file.
- Reviewing data stored in the OpenEdge Management Trend Database.

The main menu bar

The **Alerts** menu bar category maintains an up-to-date running total of the present number of not-yet-viewed, or **unseen**, alerts. Wherever you are in the management console, you can always see this information at a glance.

Figure 2–3 shows the main menu bar with a total of 2 unseen Alerts identified. As each alert’s details are viewed on individual **Alert details Summary** pages, this total is reduced by one. See the “[The detail frame](#)” section on page 2–13 for more information about the summary page.



Figure 2–3: Number of alerts unseen total on the main menu bar

In the list frame

Select either **Alerts** or **Resources** from among the console’s menu bar categories to display specific resource alert details in the list frame. Note that regardless of which of these two options you use, alerts display in association with a specific resource as identified by the resource naming convention, *container name:resource name*.

Selecting the Alerts category

Figure 2–4 shows the contents of the list frame when you select **Alerts** on the menu bar. Icons related to an alert’s severity level appear to the left of each resource name and a brief alert message appears to the right.




Figure 2–4: Outstanding alerts displayed in the Alerts list frame

The list frame supports ToolTips. ToolTips display summarized details about an alert. (Each alert’s complete contents can be displayed on the **Alert details Summary** page by clicking the resource name in the list frame). When you place your cursor over an alert icon displayed in the **Alerts** list frame, summarized alert message details appear after a few moments. Figure 2–5 shows the contents of an alert icon in the **Alerts** view of the list frame.




Figure 2–5: ToolTip details displayed on the Alerts list frame

The first alert in the list frame also simultaneously displays its alert detailed information in the detail frame. See the “[The detail frame](#)” section on page 2–13 for more information.

You can sort alerts by **Severity**, **Resource Name**, **Alert Name**, or **Last Date**. Use the drop-down menu in the **Sort by** field to change the sort criteria.

Selecting the Resources category

[Figure 2–6](#) shows the contents of the list frame when you select **Resources** on the menu bar. Icons related to an alert’s severity level appear to the left of resource names.

The figure also shows ToolTip information. Placing your cursor over an alert icon in the **Name** category of the **Resource** view in the list frame displays details related to the number of alerts and number of unseen alerts for a resource.




Figure 2–6: ToolTip details displayed on the Resources list frame

If you stop and restart OpenEdge Management, the outstanding alerts list clears. This same alert information cannot be reloaded. However, if the conditions that originally triggered the alerts still exist when OpenEdge Management restarts, new alerts are generated.

Note: Resource changes can happen very quickly, and the information contained in the **Alerts** list and the **Alerts Detail Summary** page represents the operational status of your system at the moment the information was collected. Click **Refresh** as you view alert details to ensure that you are reviewing the most current information.

For detailed information about each alert, see [Chapter 3, “Alerts Reference.”](#)

The detail frame

Detailed information about each outstanding, individual, open alert appears on its own **Alert details Summary** page, as shown in [Figure 2–7](#).

The screenshot shows the 'Alert details Summary' page for the alert 'nbaspauldixp1.Disk-0_C:: DiskBusyThresholdExceeded'. The page has a yellow header bar with a warning icon and the alert title. Below the header are five buttons: 'Previous', 'Next', 'Clear', 'Mark Unseen', and 'Bulk Clear'. The main content area is divided into three sections: 'Alert details', 'Alert Statistics', and 'Resource Statistics'. The 'Alert details' section contains a table with the following information:

Container:	nbaspauldixp1
Resource:	Disk-0_C:
Severity:	Error
Seen by:	admin
First occurrence:	May 23, 2006 9:02:37 AM
Last occurrence:	May 25, 2006 10:57:58 AM
Occurrence count:	12
Reason:	Disk Busy Threshold Exceeded! Value: 100.0, Threshold 90.0 (9618)

The 'Alert Statistics' section contains a table with the following information:

Open:	3
Unseen:	1
Last:	May 25, 2006 11:37:59 AM

The 'Resource Statistics' section contains a table with the following information:

Count:	19
Have alerts:	3
Percent:	15.78%

Below the 'Alert details' section is a text area for 'Comment for cleared alert:' with a scroll bar. At the bottom of the page is a checkbox labeled 'Confirm clearing of alerts' which is checked. The footer of the page reads 'Progress Software Corporation (www.progress.com)'.

Figure 2–7: Alert details Summary page

- ▶ To display an **Alert details Summary** page, click either an individual resource name in the list frame that has an alert icon or the link in the alert box that displays on a resource's **Resource Monitoring Summary** page.

The **Alert details Summary** page is comprised of:

- Navigational and task buttons.
- Alert details for the individual alert.
- General alert data for all outstanding alerts.

The remaining information in this section describes each of these elements. For information about clearing an individual alert, see the "[Clearing individual alerts](#)" section on page 2–22.

Navigating the Alert details Summary page

Table 2–2 identifies and describes the buttons on the **Alert details Summary** page that allow you to navigate the alerts.

Table 2–2: Alert details Summary page buttons

Click . . .	To . . .
Previous	Display the previous alert on the Alert details Summary page.
Next	Display the next alert on the Alert details Summary page.
Clear	Clear an alert that is currently displayed.
Mark Seen/Unseen	Mark the current alert as seen or unseen. Quick reference information about Unseen alerts displays as a total number next to the Alerts category on the menu bar. Seen and Unseen alert status also displays on individual alerts in the Resource list frame view when you use ToolTips. See the “ The main menu bar ” section on page 2–11 and the “ Selecting the Resources category ” section on page 2–12 for more information.
Bulk Clear	Display a page from which you can clear all alerts that meet defined criteria. See the “ Clearing alerts in bulk ” section on page 2–23 for details about the Bulk Clear process.

Alert details

Alert details include the following information:

- **Container** — The name of the resource container. You can click this link to display the container’s detail page.
- **Resource** — The resource’s name. You can click this link to display the resource’s detail page.
- **Severity** — The severity level of the alert: Severe, Error, Warning, or Information.
- **Seen by** — Who has viewed the alert.
- **First occurrence** and **Last occurrence** — When the alert was first and last noticed by OpenEdge Management.
- **Occurrence count** — The total number of times the alert has been generated. An alert can be triggered many times if a given condition exists, but the action that is associated with the alert will be run only when the alert is initially triggered. OpenEdge Management increments the **Occurrence count** field for this initial triggering and each subsequent triggering of an alert.
- **Reason** — The reason the alert occurred.

If you intend to clear an alert, you can optionally enter some relevant text about the alert in the space provided. The **Confirm clearing of alerts** option is selected by default. When you click **Clear** to remove an alert, OpenEdge Management automatically asks you to confirm that you want to clear the alert. If you do not want to confirm clearing an alert, remove the check mark from the **Confirm clearing of alerts** check box. See the “[Clearing alerts through the management console](#)” section on page 2–21 for more information.

General Alert Statistic and Legend

The **Alert Statistics**, **Resource Statistics**, and **Legend** sections provide data relevant to all outstanding alerts. The following list briefly describes each of these sections:


- **Alert Statistics** — Displays a running tally of the number of open and unseen alerts. The **Last** field displays the date and time that the last alert occurred.
- **Resource Statistics** — Displays a running tally of the number of monitored resources across all containers, the total number of alerts currently registered, and the percentage of the alerts per total number of resources.
- **Legend** — Displays static reference details that identify the specific icon with its associated severity level. Depending on the page you are displaying in OpenEdge Management, either the icon or its associated text is used to identify severity.

Views defined for collection pages

You can display outstanding alert details in views defined for a collections page.

Resources with alerts viewlet

Collections allow you to define the contents of the **Resources with alerts** standard viewlet. The viewlet displays a list of resources in a collection that currently has one or more outstanding alerts. [Figure 2–8](#) shows an example of the **Resource with alerts** viewlet.





Resource	First Alert	Last Alert	Total
 nbaspauldixp1.CPU	May 23, 2006 3:12:42 PM	May 25, 2006 9:02:57 AM	1
 nbaspauldixp1.Disk-0_C	May 23, 2006 9:02:37 AM	May 25, 2006 10:57:58 AM	1

Figure 2–8: Resource with alerts viewlet

For each resource defined as a collection member in a specific collection view, this viewlet displays an alert icon to indicate the alert’s severity (if multiple alerts exist for a single resource, the worst severity is shown).

The **Customize Viewlet** icon appears in the upper-right corner of [Figure 2–8](#). Click the icon to modify the criteria associated with this viewlet. For details about how to change this criteria, see the “[Customizing alert details](#)” section on page 2–17.

Collection members viewlet

Figure 2–9 shows a **Collection members** viewlet which is also a standard viewlet whose contents you can define.





Collection members		
	Name	Description
	nbaspauldixp1.CPU	Default CPU resource
	nbaspauldixp1.Disk-0_C_	Default disk resource
	nbaspauldixp1.FileSys-C_	Default file system resource
	nbaspauldixp1.Memory	Default memory resource


Figure 2–9: Collection members viewlet sample

For each resource defined as a collection member in a specific collection view, the viewlet can display an alert icon to indicate an alert exists and to identify the alert's severity (if multiple alerts exist for a single resource, the worst severity is shown). To display more specific details about a resource, select the individual resource link and display the resource's monitoring plan.

Alert severity legend viewlet



You can display the **Alert severity** legend on any collection view. This legend identifies the severity level identified by each alert icon.





Figure 2–10 shows a sample customized view of a **My Collections** page that includes standard viewlets for **Resources with alerts**, **Collection members**, and **Alert severity**.



The screenshot shows a web interface titled "My Collections.Home.Databases.System:Default" with a timestamp of "May 25, 2006 11:58:48 AM". Below the title bar is a "Collection View" tab. The main content area is divided into three sections:

- Resources with alerts:** A table with columns: Resource, First Alert, Last Alert, and Total.

Resource	First Alert	Last Alert	Total
 nbaspauldixp1.CPU	May 23, 2006 3:12:42 PM	May 25, 2006 9:02:57 AM	1
 nbaspauldixp1.Disk-0_C_	May 23, 2006 9:02:37 AM	May 25, 2006 10:57:58 AM	1
- Collection members:** A table with columns: Name and Description.

Name	Description
 nbaspauldixp1.CPU	Default CPU resource
 nbaspauldixp1.Disk-0_C_	Default disk resource
 nbaspauldixp1.FileSys-C_	Default file system resource
 nbaspauldixp1.Memory	Default memory resource
- Alert severity:** A legend on the right side showing four levels: Severe (red circle with exclamation mark), Warning (yellow diamond with exclamation mark), Error (yellow triangle with exclamation mark), and Information (blue square with exclamation mark).

At the bottom of the page, it says "Progress Software Corporation (www.progress.com)".

Figure 2–10: A customized view of the My Collections page

For more information about defining the content and layout of customized views, see the appropriate sections in the *OpenEdge Management: Resource Monitoring Guide*.

Customizing alert details

Collections support different options that allow you to tailor the alert details that display on a collections page. From the options available on the **Customize Viewlet** page, you can modify what appears in the **Resource with alerts viewlet** that displays on a main collections page.



To customize alert and resource details on a collections page:

1. Click the **Customize Viewlet** icon that appears in the upper-right corner of the **Resources with alerts** standard viewlet. The **Customize Viewlet** page appears:

Customize Viewlet: "Resources with alerts"

Save Cancel

Properties

Resources with alerts to show:

- ☐ All resources in project
- ☐ All resources in collection
- ☒ All resources in collection and its descendants

Fields to display

Field	Description
<input checked="" type="checkbox"/> First Alert	Date and time first alert occurred on resource
<input checked="" type="checkbox"/> Last Alert	Date and time last alert occurred on resource
<input checked="" type="checkbox"/> Total	Total number of open alerts on resource

2. Select one of the following options in the **Resources with alerts to show** section:
 - **All resources in project** — Includes all resources in OpenEdge Management whether a resource is in a collection or not.
 - **All resources in collection** — Limits resource inclusion to those resources defined for a specific collection.
 - **All resources in collection and its descendants** — Identifies resources in a collection and resources defined in sub-collections associated with the collection.
3. Select a maximum of three options in the **Fields to display** section. By default, all three options are selected. To deselect any option, click the checkmark.
4. Click **Save**.

Any changes you make to **Resources with alerts to show** and **Fields to display** settings display in the **Resources with alerts** viewlet the next time you display the collections page.

The Resource Monitoring Summary page

Figure 2–11 shows an example of how OpenEdge Management displays alerts associated with an individual resource on the **Resource Monitoring Summary** page.




Figure 2–11: Alerts associated with a specific active resource monitor



To display additional details about alerts noted in the **Alerts** box, either:

- Place your cursor over the alert icon. Momentarily, summarized alert information displays. This information is available through the ToolTips option.
- Click the individual alert link. Complete alert data displays on the **Alert details Summary** page.

E-mail notifications

If you elect to define an action for an alert, you can choose to send e-mail notifications to one or more recipients you set up during the initial OpenEdge Management configuration. The content of the e-mail message is similar to the data that displays on the **Alert details Summary** page.

OpenEdge Management supplies these default e-mail actions, each of which you can customize:

- **Default_Clear_Action.**
- **Default_Mail_Action.**
- **Default_Pager_Action.**



To access the default e-mail actions:

1. Select **Library** from the menu bar.
2. In the **Sort by** option, select **Type** and click **Actions** in the list frame.
3. Click **Email Action** from among the actions listed in the detail frame. The **Email Action** page appears in the detail frame, as shown:

Name	Description
Default Clear Action	Default Email action for use by rules and resources. This may be modified but cannot be deleted or renamed.
Default Mail Action	Default Email action for use by rules and resources. This may be modified but cannot be deleted or renamed.
Default Pager Action	Default Email action for small display devices (like pagers) for use by rules and resources. This email action may be modified at any time.

The e-mail that the recipient receives in an electronic mail box, PDA, or other electronic device also contains links to OpenEdge Management, a link to the resource involved, and a link to alert details as they display on the **Alert details Summary** page. From the **Alert details Summary** page, you can review and process the information, as needed.

See the *OpenEdge Management: Resource Monitoring Guide* for details about initiating e-mail notifications and changing the content and format of e-mail messages.

OpenEdge Management reports

From the **Reports** menu on the menu bar, you can create and display report information related to alerts and alert information trended to the OpenEdge Management Trend Database. The **Realtime Reports** and **Report Templates** categories provide access to various report detail and summary reports you can generate. Figure 2–12 shows a typical display in the list frame when you select **Reports** in the menu bar.




Figure 2–12: Expanded Reports categories

For example, the **Open Alert Detail** and **Open Alert Summary** report options under **Realtime Reports** help you examine all outstanding alerts at a glance. Under the **Report Templates** category, you can use predefined templates such as **alertGeneral** and **alertIndividual** to analyze alerts. For procedures you can use to access and run these reports, see the [OpenEdge Management: Reporting Guide](#).

The OpenEdge Management log file

All alert types are logged in the OpenEdge Management log file. (Since OpenEdge Management runs as a managed process within the AdminServer, the OpenEdge Management log file is the AdminServer log file.) An entry is added to the log file whenever an alert is either generated or cleared.

Note: Alerts are logged in the OpenEdge Management log file only if they are generated. If polling or alerting options are turned off, alerts are not generated.



To access the OpenEdge Management log file:

1. Select **Reports** on the menu bar. The **OpenEdge Management Reports** categories display in the list frame.
2. Select **Diagnostic Reports** from the categories listed. The detail page for the **Diagnostic Reports** category displays in the detail frame.
3. Select the **AdminServer Log File** link to display the AdminServer log file, as shown:

The screenshot shows the 'File: admserv.log AdminServer Log File' window. It includes navigation buttons (First, Prior, Next, Last, Reload), a 'Go To' field, and display settings (Show: 20, Overlap: 2, Display: Ascending). A summary box on the right shows log statistics. The main area displays a list of log entries with timestamps and messages.

Line	Timestamp	Severity	Source	Message
2,377	[10/6/06 8:30:04 AM]	[3]	[Fathom]	Quartz scheduler 'FathomTaskSc
2,378	[10/6/06 8:30:04 AM]	[3]	[Fathom]	Quartz scheduler version: 1.3.2
2,379	[10/6/06 8:30:04 AM]	[3]	[Fathom]	Scheduler FathomTaskScheduler_5
2,380	[10/6/06 8:30:05 AM]	[3]	[Fathom]	Report stylesheet cache success
2,381	[10/6/06 8:30:05 AM]	[3]	[Fathom]	Report stylesheet cache success
2,382	[10/6/06 8:30:06 AM]	[3]	[Fathom]	Report stylesheet cache success
2,383	[10/6/06 8:30:06 AM]	[3]	[Fathom]	Report stylesheet cache success
2,384	[10/6/06 8:30:06 AM]	[3]	[Fathom]	Report stylesheet cache success
2,385	[10/6/06 8:30:06 AM]	[3]	[Fathom]	Report stylesheet cache success
2,386	[10/6/06 8:30:06 AM]	[3]	[Fathom]	Fathom probe started. (10147)
2,387	[10/6/06 8:30:06 AM]	[3]	[Fathom]	Cleaning set for Fathom log dir
2,388	[10/6/06 8:34:51 AM]	[0]	[Fathom]	* Alert! Alert Name: DiskBusyThre
2,389	[10/6/06 8:34:51 AM]	[3]	[Fathom]	Invoking E-mail action. Action:
2,390	[10/6/06 9:37:38 AM]	[3]	[Fathom-GRAPH]	Graphing using Java V1.4 suppor
2,391	[10/6/06 9:37:40 AM]	[3]	[Fathom-GRAPH]	Java font families available: /
2,392	[10/6/06 9:37:40 AM]	[3]	[Fathom-GRAPH]	Graph font family set to: Seris
2,393	[10/6/06 9:38:08 AM]	[3]	[Fathom]	Job: truncateb11 started.
2,394	[10/6/06 9:38:09 AM]	[3]	[Fathom]	Job: truncateb11 ended, exit st
2,395	[10/6/06 11:02:07 AM]	[3]	[STDERR]	tso.getLongElement(): no data
2,396	[10/6/06 11:02:07 AM]	[3]	[Fathom]	Alert Cleared! Alert Name: Dis

The OpenEdge Management Trend Database

Like data from several other sources in OpenEdge Management, all alert data that is generated is stored in the OpenEdge Management Trend Database. However, alerts are trended only if the following conditions exist:

- The polling and alerting options are turned on so that OpenEdge Management can generate alerts.
- The trending option is turned on so that OpenEdge Management can trend the alert-generated data.

For details about alert data stored in the Configuration Data tables associated with the OpenEdge Management Trend Database, see the *[OpenEdge Management: Trend Database Guide and Reference](#)*.

Clearing alerts through the management console

You can manually clear alerts through the management console or the command-line interface. This section describes how to clear alerts manually through the management console. For details about clearing alerts using the command-line interface, see the “[Accessing alert information from the command-line interface](#)” section on page 2–28.

You can also set the **Clear alert after** property of an alert so that the alert is automatically cleared when the condition that caused the alert no longer exists. See the “[Configuring rules for individual resources](#)” section on page 2–4 for more information.

Clearing individual alerts

OpenEdge Management supports clearing individual alerts.



To clear an alert through the management console:

1. In the **Alerts** list displayed in the list frame, click the alert you want to clear. The individual alert page appears on the **Alert details Summary** page in the detail frame:

The screenshot shows the 'Alert details Summary' page for an alert titled 'nbaspauldixp1.Disk-0_C:: DiskBusyThresholdExceeded'. At the top, there is a yellow warning icon and the alert title. Below this are five buttons: 'Previous', 'Next', 'Clear', 'Mark Unseen', and 'Bulk Clear'. The main content area is divided into three sections: 'Alert details', 'Alert Statistics', and 'Resource Statistics'. The 'Alert details' section lists various attributes: Container (nbaspauldixp1), Resource (Disk-0 C:), Severity (Error), Seen by (admin), First occurrence (May 26, 2006 8:02:55 AM), Last occurrence (May 26, 2006 8:23:01 AM), Occurrence count (2), and Reason (Disk Busy Threshold Exceeded! Value: 100.0, Threshold 90.0 (9618)). The 'Alert Statistics' section shows Open: 2, Unseen: 1, and Last: May 26, 2006 9:03:07 AM. The 'Resource Statistics' section shows Count: 19, Have alerts: 2, and Percent: 10.52%. Below these sections is a text area for 'Comment for cleared alert:' and a checkbox labeled 'Confirm clearing of alerts' which is checked. At the bottom, there is a footer for Progress Software Corporation with the website URL www.progress.com.

2. Enter a comment, if you want, about the alert you are clearing.
3. Determine if you want to use the **Confirm clearing of alerts** option, which is selected by default. If you retain this default option, a confirmation window appears asking if you want to clear all selected alerts.

Otherwise, deselect the **Confirm clearing of alerts** option.

4. Click **Clear**. If you retained the **Confirm clearing of alerts** option in [Step 3](#), click **OK** to confirm that you want to clear this alert. Otherwise, OpenEdge Management automatically clears the alert and it is removed from the list and detail frames.

Note: **Mark Seen** allows you to track who viewed each alert. The **Seen by** field lists the name of the user who first views the alert. When chosen, the **Mark Seen** button label becomes **Mark Unseen**, which allows you to change the seen status of the alert.

Clearing alerts in bulk

OpenEdge Management provides an option to clear alerts in bulk from the **Clear Alerts** page, as shown in [Figure 2–13](#).

Figure 2–13: Clear Alerts page

The **Clear Alerts** page displays when you select **Bulk Clear** on the **Alert details Summary** page. It consists of the **Alert selection criteria** section and the **Comment for cleared alert(s)** section that is identical to the **Comments** section on the **Alert details Summary** page.

To clear alerts in bulk, you must set up one of four options that OpenEdge Management uses to remove qualifying alerts. [Table 2–3](#) describes these options.

Table 2–3: Bulk Clear criteria options

To clear alerts . . .	Select . . .
By resource.	A resource name from the associated drop-down list (the default selection).
By container.	A container name from the associated drop-down list.
By alert type.	An alert type available in the associated drop-down list.
Prior to some date and time.	A date using dd/mm/yyyy format and specific time of day.

The **Confirm clearing of alerts** option displays as a default on the **Clear Alerts** page. If you retain this option, OpenEdge Management prompts you to confirm the removal of all existing alerts that meet the criteria option that you selected, as shown in [Figure 2–14](#).



Figure 2–14: Confirm Clearing Alerts page

Click **OK** to remove all alerts simultaneously. Deselect any alerts that you do not want to clear at this time.

After all alerts have been cleared, a confirming message displays, as shown in [Figure 2–15](#).



Figure 2–15: No open alerts message

The unseen alert count as noted in the menu bar next to the **Alerts** category will display a total of zero unseen alerts at this time.

Disabling alerts

Sometimes you might want to disable alerts, such as when you know your database is going to be unavailable due to a dump and load or another procedure.

There are three ways to disable alerts to prevent OpenEdge Management from generating them:

- Disable alerts in a monitoring plan. This method allows polling of your resources to continue.
- Disable an individual resource. This method does not allow your resource to be polled.
- Disable all alerts (that is, polled, asynchronous, and internal alerts) on the **OpenEdge Management Resource Monitoring Configuration** page.

Disabling alerts in a monitoring plan

The steps you perform to disable alerts in a monitoring plan apply to all resource types being monitored.



To disable an alert on a specific rule:

1. Select **Resources** on the menu bar.
2. From the list of resources displayed, click the resource whose alert feature you want to disable. The **Resource Summary** page appears:

Log File: nbaspauldixp1.log_file_ex ❌ Failed (1 Hour)
 Last Poll: May 26, 2006 9:13:08 AM
 Last Failure: May 26, 2006 9:13:07 AM
 Poll Count: 16 Fail Count: 16 (100.0%)

Edit Copy Delete Log File Viewer

Alerts
 ⚠ LogFileNotFound May 26, 2006 9:13:07 AM

Properties
 Filename: logfileex.log
 On First Poll: Search only new data
 Bookmark: "Fathom_Bookmark"
 Timestamp will be prepended

Monitoring plans

Name	Poll	Alerts
Default_Schedule_Plan	5 mins	✓

Edit

Rule Summary

Name	Status	Severity
System_Error	Not Checked	
DB_Shutdown	Not Checked	

Add Plan

Progress Software Corporation (www.progress.com)

3. Click **Edit** associated with the **Default Schedule Plan** field. The **Edit Resource Monitoring Plan** page appears:

Edit Default_Schedule Monitoring Plan for: nbaspauldixp1.log_file_ex

Save Cancel

Monitoring plan definition

Available Schedules: Default_Schedule

Polling Interval: 5 minutes

Alerts Enabled: ☒

Rules selected for this plan

Name	Status	Severity
System_Error	Not Checked	
DB_Shutdown	Not Checked	

Add Rule Select Rule Sets

Progress Software Corporation (www.progress.com)

4. Clear the **Alerts Enabled** check box to disable alerts.
5. Click **Save**.



To disable all alerts in a monitoring plan for a resource:

1. Select **Resources** on the menu bar.
2. From the list of resources displayed, click the resource whose alert feature you want to disable. For example, you may want to disable all alerts for a particular database.
3. Click **Monitoring Plans** in the **Command and Control** section of the **Database** resource page. The resource's **Monitoring Plans** summary page appears:

Database: Sports2006 Monitoring Plans

Monitoring plans			
Name	Poll	Alerts	Trend
Default Schedule Plan	5 mins	✓	✓

[Edit](#)

Rule Summary

Name	Status	Severity
Default DB RuleSet	---	---
Abnormal Shutdown	Passed	
Agent Abnormal Shutdown	Passed	
Busy BI Buffer Waits High	Passed	
Empty AI Buffer Waits High	Passed	
Stopped Trending	Passed	

[Add Plan](#)

Progress Software Corporation (www.progress.com)

4. Click **Edit**. The resource's **Edit Monitoring Plan** page appears:

Edit Default_Schedule Monitoring Plan for: nbaspauldixp1.Sports2006

[Save](#) [Cancel](#)

Monitoring plan definition

Available Schedules: [Default_Schedule](#)

Polling Interval: [minutes](#)

Alerts Enabled: ☒

Trend Performance Data: ☒ [Advanced Settings](#)

Rules selected for this plan

Name	Status	Severity
Default DB RuleSet	---	---
Abnormal Shutdown	Passed	
Agent Abnormal Shutdown	Passed	
Busy BI Buffer Waits High	Passed	
Empty AI Buffer Waits High	Passed	
Stopped Trending	Passed	

[Add Rule](#) [Select Rule Sets](#)

Progress Software Corporation (www.progress.com)

5. Clear the **Alerts Enabled** check box to disable alerts. Alerts will not be generated, but monitoring activities continue and the resource's status continues to be updated.
6. Click **Save**.

Disabling an individual resource monitor

Disabling an individual resource monitor prevents any monitoring activities from occurring for that resource. When a resource is disabled using this procedure, all resource polling, alert generation, and information trending ceases. Resource monitors that are currently disabled are easily identified in the management console. A gray **Resource Status** icon precedes the resource's name when the resource appears in the list frame.

The method used to disable resources depends on whether the resource is a system, network, or file resource, or a database or an OpenEdge server resource.



To disable a system, network, or file resource monitor:

1. In the **Resource** list, click the resource to be disabled. The **Resource Summary** page appears in the detail frame.
2. Click **Edit** at the top of the resource page. The **Properties** section displays in the **Edit Resource** page.
3. Clear the **Enabled** check box.
4. Click **Save**. When you refresh the list frame, the color of the **Resource Status** icon for the disabled resource changes to gray.



To disable a database or an OpenEdge resource monitor:

1. In the **Resource** list, click the resource to be disabled. The **Database Control** page (or **OpenEdge main** page for an OpenEdge server resource monitor) appears.
2. Click **Control** (for database or NameServer resources) or **Broker Control** (for WebSpeed or AppServer resources). A summary page for the resource monitor you selected appears.
3. Click **Edit**. Clear the **Enabled** check box to disable the database resource.
4. Click **Save**. When you refresh the list frame, the color of the **Resource Status** icon for the disabled OpenEdge resource changes to gray.


Disabling alerts for all resources

You can disable the appearance of all types of alerts—polled, asynchronous, and internal—from display in OpenEdge Management.



To disable alerts:

1. Click **Options** on the menu bar. The list of options appears in the list frame.
2. Choose **Configuration→ Resource Monitoring** in the list frame. The **OpenEdge Management Resource Monitoring Configuration** page appears in the detail frame:



3. Clear the **Generate alerts** check box.

Accessing alert information from the command-line interface

OpenEdge Management provides a command-line interface that performs OpenEdge Management functions without the use of the graphical user interface. Specifically, the command-line interface allows you to:

- Start, query, and stop OpenEdge Management.
- Clear an alert.
- Use other alert commands (`firealert` and `alertlist`).
- Access command-line help.

You can also use the command-line interface to manage the OpenEdge Management configuration database. For details on the backup and restore commands you can enter on the command-line and other commands you can enter in the command line for administrative purposes, see the appropriate section of the *OpenEdge Management: Installation and Configuration Guide*.

The OpenEdge Management environment window

As a convenience, you can execute command-line utilities from an OpenEdge Management environment window. Access this window by choosing **Start→Programs→OpenEdge Management→Set OpenEdge Management Environment**. The environment window sets the shell environment variables needed for executing both OpenEdge Management and OpenEdge commands, as shown in [Figure 2–16](#).




Figure 2–16: Set OpenEdge Management Environment window

Starting, querying, and stopping OpenEdge Management

Use the following syntax to start, query, or stop OpenEdge Management from the command line:

```
fathom [-start | -query | -stop] [options]
```

[Table 2–4](#) describes the options you can use when starting or stopping OpenEdge Management.

Table 2–4: Options for starting and stopping OpenEdge Management

Option syntax	Description
-host <host>	Host where the AdminServer process resides.
-port <port>	Port where the AdminServer runs. Default is 20931.
-timeout <time>	Time, in seconds, for OpenEdge Management to wait for a response. Default is 240 seconds.
-user <user-name>	Username on machine where the AdminServer resides. Default is current user.
-password <user-password>	Password associated with the specified username. Not needed for a local connection. Note: Use of the -password parameter might allow others to see your password in readable, clear text.

Examples

You want to connect to your AdminServer but you do not want to wait more than five minutes for the connection to be made. Enter the following syntax to start OpenEdge Management from the command line:

```
fathom -start -timeout 300
```

Enter the following syntax to stop OpenEdge Management from the command line and specify that the command-line interface tool wait five minutes before reporting an error:

```
fathom -stop -timeout 300
```

To learn the execution status of OpenEdge Management with an AdminServer port number of 1905, enter the following syntax:

```
fathom -query -port 1905
```

Clearing an alert

To clear an alert from the command line, use the following syntax:

```
fathom [-httpport <port-number>] -clear [option] [-comment '<comment text>']
```

Note: You specify `-httpport` only if OpenEdge Management is running on a port other than the default of 9090.

Table 2–5 lists options to use with the `fathom -clear` command.

Table 2–5: Clear alert command options

(1 of 3)

Option syntax	Purpose	How to use
<code>-httpport <port-number></code>	Use to identify the port number if it is not the default port of 9090.	Provide the <code>-httpport</code> option followed by the port number.
<code>-comment '<comment-text>'</code>	Use to provide a comment when clearing an alert.	Provide the <code>-comment</code> option followed by the comment text. The text must be enclosed in single quotation marks.

Table 2–5: Clear alert command options

(2 of 3)

Option syntax	Purpose	How to use
<code>-alert <alert-name></code> <code>[-container <container>] </code> <code>[-resource <resource>] </code> <code>[-restype <resource type>]</code>	Use to clear all instances of a particular alert for one specific resource, or for all resources within a specific container.	<p>Provide the <code>-alert</code> command followed by the alert name. Then provide either the resource name or the resource type. Options are defined as follows:</p> <ul style="list-style-type: none"> • -container — The name of a container as defined in OpenEdge Management. • -alert — The name of the alert as defined in OpenEdge Management. • -resource — The name or the reference key of the resource as defined in OpenEdge Management. See the “Using the alertlist command with additional options” section on page 2–36 for details about the reference key. • -restype — The resource type. The type of resource is limited to one of the following: database, file, network, openedge, or system.

Table 2–5: Clear alert command options

(3 of 3)

Option syntax	Purpose	How to use
<code>-alertid <alert id number></code>	Use to clear an alert by its number (regardless of the resource or its type).	Provide the <code>-alertid</code> option followed by its number.
<code>-all</code> <code>[-restype <resource type>] </code> <code>[-resource <resource>] </code> <code>[-alert <alert name>] </code> <code>[-container <container>] </code> <code>[-severity <severity>]</code>	Use to clear: <ul style="list-style-type: none"> • All alerts. • All alerts for a particular resource type. • All alerts for a particular resource. • All instances of a particular alert for all resources. • All alerts for a specific container. • All alerts for a specific severity. 	Provide the <code>-all</code> command without an option to clear all alerts, or with one of these options to clear particular alerts: <ul style="list-style-type: none"> • -restype — The resource type. The type of resource is limited to one of the following: database, file, network, openedge, or system. • -resource — The name or the reference key of the resource as defined in OpenEdge Management. See the “Using the alertlist command with additional options” section on page 2–36 for details about the reference key. • -alert — The name of the alert as defined in OpenEdge Management. • -container — The name of a container as defined in OpenEdge Management. • -severity — The alert severity: Severe, Error, Warning, or Informational.

Example

OpenEdge Management polls your Sports2000 database and sends an alert for Record Waits High (the alert sent when waits for records are above a defined threshold). To clear this alert from the command line, enter:

```
fathom -httpport 8080 -clear -alert RecordWaitsHigh -comment 'Cleared by Admin'
```

Note: You specify `-httpport` only if OpenEdge Management is running on a port other than the default of 9090.

Other alert commands

OpenEdge Management supports the following alert commands:


- `-firealert`
- `-alertlist`

Using the `-firealert` command

Use the following syntax to fire an alert:

```
fathom -firealert [alertmessage]
```

OpenEdge Management also supports generation of application-specific alerts. In your application, you can send alerts to OpenEdge Management using the `-firealert` options shown in Figure 2-17.



```

Set OpenEdge Management Environment
Appending ...
DLC: C:\Progress\OpenEdge\bin
FATHOM: C:\Progress\Fathom\bin
to the PATH.

OpenEdge Release 10.1B1P as of Tue Sep 26 02:28:14 EDT 2006
Fathom Version 3.1B1P as of Mon Sep 25 03:18:29 EDT 2006
proenv>fathom -firealert -help
Fathom Version 3.1B1P as of Mon Sep 25 03:18:29 EDT 2006

Usage: fathom -firealert <alertName> -resource <resource name> [<options>]

Any, none, or all of the following options may be used:
  -httpport <portno> -action [<actionName>] -msg '<message>'
  -who <username> -threshold <threshold number>
  -value <trigger value>

httpport  The HTTP port that fathom is running on, default is 9090
action     The name of a defined action in Fathom or nothing.
msg        The description of the alert enclosed in single quotes. Default
           is blank.
who        The username to be placed into the trend database as the person
           generating the alert.
threshold  The number representing the threshold compared for the alert.
value      The number which triggered the alert.
severity   The severity of the alert:
           1 = Severe (Default)
           2 = Error
           3 = Warning
           4 = Information

proenv>_

```


Figure 2-17: `-firealert` command options

Example

You want to fire an alert regarding the CPU. Enter the following on the command line:

```
fathom -firealert JOBFAILED -resource CPU -msg 'JOB XYZ FAILED'
```

The alert fires, as shown in Figure 2-18.



```

Set OpenEdge Management Environment
proenv>fathom -firealert JOBFAILED -resource CPU -msg 'JOB XYZ FAILED'
Fathom Version 3.1B1P as of Mon Sep 25 03:18:29 EDT 2006

Alert Fired. ID: 4

proenv>_

```

Figure 2-18: Firing an alert

You can then look at the alert details for the CPU. Enter the following on the command line:

```
fathom -alertlist -detail -resource CPU
```

The alert details appear, as shown in [Figure 2–19](#).




Figure 2–19: -firealert command example

Using the -alertlist command with group selection options

You can display an alert list by specifying one of the -alertlist command group selection options on the command line. [Table 2–6](#) identifies and describes each group selection option.

Table 2–6: Alert list command group selection options

Option syntax	Purpose	How to use
-alert	To view a list of all instances of a particular alert.	Provide the name of the alert you want to see.
-resource	To view a list of alerts for a particular resource.	Provide the name of the resource whose alerts you want to see listed.
-container	To view alerts associated with a specific container.	Provide the name of the container whose alerts you want to see listed.
-restype	To view a list of alerts for a particular resource type.	Provide the resource type whose alerts you want to see listed. The resource type is limited to one of the following: database, file, network, system, or openedge.
-severity	To view a list of alerts of a particular severity.	Provide the severity level of alerts you want to see listed: severe, error, warning, or informational.

Use the following syntax to display an alert list:

```
fathom -httpport 8080 -alertlist [group selection option] [keyword value]
```

Note: You specify `-httpport` only if OpenEdge Management is running on a port other than the default of 9090.

You can also use two additional options, the `-detail` and `-verbose` options, presented in [Table 2-7](#), with the group selection options highlighted in [Table 2-6](#).

Although the command line does not limit the number of options you can type into the command line, only the last group selection option identified on the command line is processed.

[Figure 2-20](#) identifies a command line that generates a group selection based on the `-restype` option where the resource type is identified as system. Note that the resource name, listed in the **Resource** column, specifies the container name and associated resource name. Although this level of detail provides more information about a resource, it does not completely eliminate the possibility of confusion among resources with similar or identical names.




Figure 2-20: `-restype` group selection option results

Using the alertlist command with additional options

Table 2-7 identifies and describes the additional options `-detail` and `-verbose`.


Note: Unlike the group selection options highlighted in Table 2-6, the `-detail` and `-verbose` options will be processed regardless of the position in which you enter them on the command line.

Table 2-7: Alert list command options to display additional details

Option syntax	Purpose	How to use
<code>-detail</code>	To format the display to provide a block of information about the alert, shown in the command line. The block of information matches what you see when you display the alert in the console. See Table 2-8 for a summary of the alert list details.	Provide the <code>-detail</code> option along with the option whose alert information you want to see listed.
<code>-verbose</code>	To change the resource column of the displayed alerts from the generic format <i>container:resource</i> name to the fully qualified resource key. See Figure 2-21 to see an example of how to use the <code>-verbose</code> option.	Provide the <code>-verbose</code> option along with the option whose alert information you want to see listed.

Figure 2-21 identifies a command line that generates a group selection based on the `-restype` option that also includes the `-verbose` option. Note that the resource name, listed in the **Resource** column, specifies the *fully qualified resource key*. A fully qualified resource key is the most complete reference to a resource. The default format for a fully qualified resource key identifies each resource by its container name, the resource category to which the resource belongs, and the specific resource type and associated resource name.

In Figure 2-21, the fully qualified resource key information identifies **localhost** as the container, the resource category as **system**, and the specific **cpu** resource name as **CPU**.



```

Set OpenEdge Management Environment
proenv>fathom -alertlist -restype system -verbose
Fathom Version 3.1B1P as of Mon Sep 25 03:18:29 EDT 2006

ID      Severity  Alert Name      Resource
-----
4       Severe     JOBFRAILED      localhost:resource.system.cpu.CPU

proenv>_

```

Figure 2-21: `-restype` group option with verbose option results

Note: The container name **localhost** is logically the same as the container name for the system where OpenEdge Management is installed and running.

Use the fully qualified resource key to:

- Ensure that you are not confusing one resource name with another one that is either identical or similar. For example, it is possible to confuse a `wsbroker1` on one container with another `wsbroker1` on a different container. Referencing a resource by its explicit fully qualified resource key eliminates confusion as to what resource you are working with.
- Provide easy access to the complete resource information. You can cut and paste the fully qualified resource key into the command line when you use the `-resource` group option.

Note: Due to the use of the colon in the fully qualified resource key between the container name and the resource category information, this format might need to be put in quotation marks on UNIX systems.

Table 2–8 lists the details that can appear in the alert list.

Table 2–8: Alert list details


Name	Description
Alert ID	The number given to the alert.
Alert name	The name of the alert.
Alert severity	Whether the alert is considered an error, a warning, or informational or severe in nature.
Alert message	The content of the alert message. For example, notification that the Database Resource known as the OpenEdge Management Trend Database has been enabled.
Alert count	The number of times the alert has occurred.
Container	The name of the container to which the resource belongs.
Resource	The name of the resource; for example, OpenEdge Management Trend Database.
Last fire date	The time and date when the alert was last fired.
First fire date	The time and date when the alert was first fired.
Has been seen?	Whether the alert has been seen yet (either <code>true</code> if it has been seen or <code>false</code> if it has not been seen).
Seen by	If the alert has been seen, the name of the user who saw it. (If the alert has not been seen, the <code>Seen by</code> field does not appear.)

Examples

Enter the following command to see a list of existing OpenEdge Management alerts from the command line:

```
fathom -alertlist
```

Information about the current alerts appears, as shown in [Figure 2–22](#).



```

proenv>fathom -alertlist
Fathom Version 3.1B1P as of Mon Sep 25 03:18:29 EDT 2006

ID      Severity  Alert Name                      Resource
-----
4       Severe     JOBFAILED                      localhost:CPU
1       Error     FileDoesNotExist               localhost:filemon1
2       Error     LogFileNotFound                localhost:lfm1

proenv>

```


Figure 2–22: -alertlist in the command line

In [Figure 2–22](#) there are three alerts. One alert exists for a CPU resource named **CPU**, one alert for a file monitor resource named **filemon1**, and one alert for a log file resource named **lfm1**. As identified in the **Resource** column, all of these resources are on the **localhost** container. The alert ID numbers (**ID**) and severity (**Severity**) are also provided.

Enter the following command for a list of alerts for all OpenEdge server resources:

```
fathom -alertlist -restype openedge
```

You see any alerts that exist for any OpenEdge server resources (**openedge**) listed. If there are no existing alerts, you receive the message shown in [Figure 2–23](#).



```

proenv>fathom -alertlist -restype openedge
Fathom Version 3.1B1P as of Mon Sep 25 03:18:29 EDT 2006

ID      Severity  Alert Name                      Resource
-----
There were no alerts of type openedge

proenv>_

```

Figure 2–23: -alertlist for openedge resource type

To see specific details about the alerts that exist for system resources, use either the **-detail** option or the **-verbose** option.

Enter the following command to examine the results of using the `-detail` option:

```
fathom -alertlist -restype system -detail
```

The details appear, as shown in [Figure 2–24](#).




Figure 2–24: `-alertlist` command used with `-detail` option

Enter the following command to examine the results of using the `-verbose` option:

```
fathom -alertlist -restype system -verbose
```

The details appear, as shown in [Figure 2–25](#).




Figure 2–25: `-alertlist` command used with `-verbose` option

OpenEdge Management internal alerts

OpenEdge Management internal alerts automatically inform you of events that occur internal to OpenEdge Management and for which you cannot set up specific alert definitions. For example, there is no option to define a rule, associated alert, and action for an internal event such as the fact that the CPU resource could not trend data to the OpenEdge Management Trend Database. In this instance, OpenEdge Management automatically triggers an alert to inform you of this internal activity.

Defining an action for all internal alerts

OpenEdge Management supports one specific option for the internal alert feature. You can select an action for OpenEdge Management to associate with all internal alerts that are triggered.



To access the action to perform on internal OpenEdge Management alerts option:

1. From the menu bar, choose **Options**.
2. Choose **Configuration**→**General**. The **OpenEdge Management General Configuration** page appears:

3. From the drop-down list box associated with the **Action to perform on internal OpenEdge Management alerts** field, select the action you want OpenEdge Management to perform in response to internally generated alerts. Actions include: **None**, **Default_Action**, **Default_Clear_Action**, **Default_Mail_Action**, **Default_Pager_Action**, or a user-defined action. For specific details about these default actions, see the section about actions in the *OpenEdge Management: Resource Monitoring Guide*.

Note: The **Generate alerts** option on the **OpenEdge Management Resource Monitoring Configuration** page governs all alerts—polled, asynchronous, or internal—that display in the management console. To enable this option for internal alerts, the **Generate alerts** option must be selected simultaneously with the **Action to perform on internal OpenEdge Management alerts** on the **OpenEdge Management General Configuration** page shown in [Step 2](#).

Reviewing and processing internal alert data

You can view and process internal alerts using the same procedures defined for all other polled or asynchronous alerts. See the “[Viewing alert information](#)” section on page 2–10 and the “[Clearing alerts through the management console](#)” section on page 2–21 for details.

Figure 2–26 shows an example of an internal alert on the detail frame page. This page is accessible from the **Alert details Summary** page.




Figure 2–26: OpenEdge Management Internal Alerts page

Note that the icon and associated header label on this page immediately identify this alert as internally generated by OpenEdge Management.

Alerts Reference

This chapter provides detailed information about the asynchronous alerts and polled alerts that OpenEdge Management can generate for asynchronous rules and polled rules, as outlined in the following section:

- [Alert organization and properties](#)

Alert organization and properties

For ease of reference, some of the alerts are listed in alphabetical order by prefix. The database- and OpenEdge-generated alerts appear in this text with these unique prefixes:

- **AppServer** — AS_
- **Database** — DB_
- **NameServer** — NS_
- **WebSpeed** — WS_

Report alerts related to report run failures are preceded by the prefix **ReportRunFailed**. Alerts that do not have a prefix are listed alphabetically by name.

Alert properties

This chapter presents the following property details for alerts:

- **Alert Name** — The name of the alert. In those instances in which the specific alert name might vary, the alert is identified in this chapter with brackets (< >).
- **Alert Message** — What the alert looks like to the recipient. Variables that appear in alert messages are identified in this reference section in italics. For example, Broker: *name*, NameServer: *NSname*, and Threshold: *threshold*.
- **Alert Description** — A description of the alert.
- **Alert Message** — What the alert looks like to the recipient.
- **Alert Type** — The type of alert: polled or asynchronous. See the “[Alert types](#)” section on page 1–3 for a detailed definition for each alert type.
- **Action** — Suggestions on what remedial actions to take.
- **Note** — Additional clarifying information about an alert.
- **See Also** — References to other manuals. These references might provide additional details about an alert, or about related functionality.

You might not see all elements listed for every alert, as some of the elements are not applicable to every alert.

<Specific Log File Rule Name>

Message	<rulename>: Text found in <file being monitored>. Rule name {# of matches}:%s
Description	Sent when the log file monitor finds one or more strings in file <i>x</i> , where <i>x</i> is the file being monitored.
Type	Synchronous
Note	The Log File Monitor within OpenEdge Management found a string or strings in the log file it is monitoring. The strings have the Log File Rule name and a number in brackets. The number represents the number of times the search string was found in a poll. The string name is the name of the rule associated with the active monitoring plan, not the search string itself.

ActionNotRun

Message	“Error running alert action. Alert: <i>x</i> , Resource: <i>y</i> , Action: <i>z</i> .”
Description	Sent when an action running in response to an alert fails due to an error. It is possible that this alert can be triggered when the OpenEdge Management Action Queue is full, indicating that when actions are invoked they are not being completed due to this full state.
Type	Asynchronous
Action	Contact Progress Software Corporation Technical Support.
Notes	<ul style="list-style-type: none"> • If you receive this alert, any recovery or notification that the action was to perform will not have occurred. • If the thread pool or queue used to run the action overflows, OpenEdge Management generates this alert.

AS_AverageProcedureDurationHigh

Message	“The average execution time of a procedure has exceeded the threshold. Threshold: <i>threshold</i> Current Value: <i>Current value</i> Procedure: <i>Procedure name</i> .”
Description	The average time spent executing a procedure during the polling interval exceeded the threshold. This situation could indicate a bottleneck in the application or other unforeseen events that inhibit the offending procedure from executing as quickly as expected.
Type	Polled
See Also	OpenEdge Management: Servers Guide

AS_BrokerAbnormalShutdown

Message	“AppServer broker shut down abnormally. Broker: <i>name</i> .”
Description	Sent when an AppServer broker shut down abnormally (crashed).
Type	Asynchronous
Action	View the appropriate log file for further information.

AS_BrokerNormalShutdown

Message	“AppServer broker shutdown normally. Broker: <i>name</i> .”
Description	Sent when an AppServer broker shuts down normally.
Type	Asynchronous

AS_BrokerStartup

Message	“AppServer broker started. Broker: <i>name</i> .”
Description	Sent when an AppServer broker starts up.
Type	Asynchronous

AS_ClientAbnormalDisconnect

Message	“A client is disconnected abnormally. Message: <i>disconnectMsg</i> .”
Description	Sent when an AppServer client connection is abnormally dropped.
Type	Asynchronous

AS_NameServerUnavailable

Message	“AppServer <i>broker</i> failed to reach the NameServer. Broker: <i>name</i> , NameServer: <i>NSname</i> .”
Description	Sent when the AppServer broker failed to contact the NameServer.
Type	Asynchronous
Action	Check the AdminServer log (admserv.log) for more information about NameServer unavailable.

AS_QueuedRequestPercentHigh

Message	“The percentage of queued requests has exceeded the threshold. Current Value: <i>value</i> , Threshold: <i>threshold</i> , Broker: <i>namename</i> .”
Description	The percentage of client requests queued during the polling interval exceeded the threshold. This situation could indicate bottlenecks or other unforeseen events that are slowing down request processing.
Type	Polled
Action	Check the AdminServer log (admserv.log) for further information about RequestQueueDepthHigh.
See Also	OpenEdge Management: Servers Guide

AS_RejectedRequestPercentHigh

Message	“The percentage of rejected requests has exceeded the threshold. Broker: <i>name</i> , Current Value: <i>value%</i> , Threshold: <i>threshold%</i> .”
Description	The percentage of client requests rejected during the polling interval exceeded the threshold. This situation could indicate bottlenecks or tuning problems, preventing client requests from being serviced.
Type	Polled
Action	Check the AdminServer log (admserv.log) for further information about Client Request Rejected and No Available Server.
See Also	OpenEdge Management: Servers Guide

AS_ServerAdded

Message	“AppServer broker added server(s). Broker: <i>name</i> , Number of servers added: <i>num</i> .”
Description	Sent when AppServer servers have been added to the pool of available servers.
Type	Asynchronous

AS_ServerKilled

Message	One of two messages can display for this alert: <ul style="list-style-type: none">• “Server killed. Server PID: <i>PID</i>.”• “Server cannot be killed at this time. Server PID: <i>PID</i>.”
Description	Sent when a user manually destroys an AppServer or AppServers. Typically a user initiates a server kill action when servers hang under a connecting status for a long time.
Type	Asynchronous
Action	If the kill request cannot be processed, check the log file.
See Also	OpenEdge Management: Servers Guide

AS_ServerTrimmed

Message	“AppServer broker trimmed server(s). Broker: <i>name</i> , Number of servers trimmed: <i>num</i> .”
Description	Sent when AppServer servers have been trimmed from the pool of available servers.
Type	Asynchronous
See Also	OpenEdge Management: Servers Guide

AS_ServerUnavailable

Message	“The server has been in an unavailable state for more than specified number of polls. Threshold: <i>threshold</i> , Number of polls: <i>number of polls</i> , PID: <i>process ID</i> .”
Description	Sent when a server has been unavailable for more than the specified number of polls.
Type	Polled
Action	Check the AdminServer log (admserv.log) for further information about ServerUnavailableTimeout.

BadSearchPattern

Message	“The search pattern provided to the HTTP Monitor’s content rule is malformed. Pattern: <i>x</i> .”
Description	Sent if the HTTP Monitor could not search downloaded content because the pattern provided did not follow the rules for regular expressions.
Type	Polled

ContextSwitchHigh

Message	“Upgrade record locks are <i>n</i> . The current threshold is <i>threshold</i> .”
Description	Sent to identify the number of times that the CPU has to switch between processes, saving the state of that process, including memory information, to ensure that it can restart that process exactly where it left off.
Type	Polled
Action	Review CPU and memory activity to determine if they are overloaded.
Note	Content switches not only deal with CPU, but also with memory consumption, paging, and swapping.

CPUBusyThresholdExceeded

Message	“CPU Busy Threshold Exceeded! Value: <i>x</i> , Threshold: <i>y</i> .”
Description	Sent when a CPU’s configured threshold is exceeded.
Type	Polled
Action	If the CPU Busy percent is continuously above the defined threshold, look for race conditions in individual processes and reduce the number of active applications. If necessary, consider upgrading CPU to a faster model.

CPUNotFound

Message	“Cannot obtain information about the CPU resource.”
Description	Sent when the CPU monitor fails to obtain valid query information for the CPU resource.
Type	Asynchronous
Action	Because the CPU monitor cannot locate the underlying CPU resource, the CPU monitor is unable to obtain information about the CPU activity. This might be related to a problem with one or more CPUs on the machine or a problem with the machine-specific library used to monitor the system resources. Check the AdminServer log (<code>admserv.log</code>) to see if the osmetrics shared library has logged errors while initializing or during operation.

DB_AbnormalShutdown

Message	“Abnormal shutdown has occurred for database <i>x</i> .”
Description	Sent when the DB_agent detects the death of the database broker.
Type	Asynchronous
Action	Check the database log file for additional information regarding the abnormal shutdown.
Note	An abnormal shutdown occurs when the database crashes or the shutdown is performed with Proshut instead of Dbman. (The Dbman command is initiated through the AdminServer, enabling the AdminServer to be aware of the shutdown activity. The Proshut command communicates directly with the database server, causing the AdminServer to assume that the database has abnormally shut down.)

DB_AgentCrash

Message	“Database Agent, <i>x</i> , crashed!”
Description	Sent when the OpenEdge Management database monitoring agent crashes. If the agent is not running, OpenEdge Management cannot monitor the database.
Type	Asynchronous
Action	Check that the database agent is still running. If it is not, restart it.

DB_AgentDown

Message	“Database agent, <i>x</i> , is shutting down.”
Description	Sent when a database agent is shut down. If the agent is not running, OpenEdge Management cannot monitor the database.
Type	Asynchronous
Action	If the agent should be running, restart it.

DB_AgentIdle

Message	“Database Agent, <i>x</i> , is not running.”
Description	Sent when a database agent is not running but the database resource is enabled. OpenEdge Management cannot monitor the database unless the agent is running.
Type	Asynchronous
Action	Go to the Database Control page for the affected database and start the agent.

DB_AgentReadError

Message	“A problem was encountered getting data from database <i>x</i> . The data will be ignored.”
Description	Sent when a problem was encountered with retrieving VST data during the polling of the database. No rules will be evaluated.
Type	Asynchronous

DB_AgentStartup

Message	“A normal string has occurred for database agent, <i>x</i> .”
Description	Sent when a database agent starts.
Type	Asynchronous

DB_AIWWritePercentLow

Message	“After-image writer percentage is <i>n</i> . The current threshold is <i>x</i> . Sample number = <i>y</i> .”
Description	Sent when the after-image writer write percent is below the configured threshold.
Type	Polled
Action	Verify that after-imaging is enabled and that there is an AIW running. Automate the checking of AIW on managed databases.
Notes	<ul style="list-style-type: none">• If the database license is Workgroup, AIW is disabled and cannot be enabled.• Information about AIWWritePercentLow is stored in the OpenEdge Management Trend Database in the Db_ActLog table.

DB_AreaSpaceUtilizationHigh

Message	“Area <i>X</i> is <i>n</i> % utilized. The threshold is <i>x</i> .”
Description	Sent when the percentage of used blocks in area <i>X</i> is high.
Type	Polled
Note	Information about DB_AreaSpaceUtilizationHigh is stored in the OpenEdge Management Trend Database.
See Also	For additional database-related information, see: <ul style="list-style-type: none">• OpenEdge Management: Trend Database Guide and Reference• OpenEdge Data Management: Database Administration

DB_AutoStartFail

Message	“Database <i>x</i> has failed to start.”
Description	Sent when the database is configured to automatically start when the AdminServer starts but does not.
Type	Asynchronous
Action	Check the database log file for additional information regarding the failed start.

DB_BIPartialWritesHigh

Message	“Before-image partial writes are <i>n</i> . The current threshold is <i>x</i> .”
Description	Sent when the number of partial writes of before-image buffers to the before-image file is above the threshold.
Type	Polled
Action	Decrease <code>-biblocksize</code> parameter to next size down or increase <code>-Mf</code> .
Note	Information about DB_BIPartialWritesHigh is stored in the OpenEdge Management Trend Database in the Db_ActLog table.

DB_BIWWritePercentLow

Message	“Before-image writer percentage is <i>n</i> . The current threshold is <i>x</i> .”
Description	Sent when the database before-image writer write percentage is below the threshold.
Type	Polled
Action	Lower BI block size.
Notes:	<ul style="list-style-type: none">• If the database license is Workgroup, BIW is disabled and cannot be enabled.• Information about BIWWritePercentLow is stored in the OpenEdge Management Trend Database in the Db_ActLog table.

DB_BrokerReconnectFail

Message	“Database broker for the specified database failed to reconnect when the AdminServer was started.”
Description	Sent when the database broker was connected and running when the AdminServer was stopped, and failed to reconnect when the AdminServer was restarted.
Type	Asynchronous

DB_BufferIOHigh

Message	“Database I/O is unusually high. The write-to-I/O ratio is <i>x</i> . The current threshold is <i>y</i> .”
Description	Sent when database writes-to-read ratio is above average.
Type	Polled
Action	Review database layout and disk subsystem performance.
Note	Information about BufferIOHigh is stored in the OpenEdge Management Trend Database in the Db_ActSum table.

DB_BuffersFlushedatCheckpointHigh

Message	“Buffers flushed at checkpoint were <i>n</i> . The current threshold is <i>x</i> .”
Description	Sent if there are database buffers that were flushed at checkpoint.
Type	Polled
Action	Verify that APWs are running. Increase the BI cluster size. Start additional APWs if only one is running.
Notes	<ul style="list-style-type: none">• If the database is a licensed workgroup, APW is disabled and cannot be enabled.• Starting additional APWs can be automated on managed databases.• The database must be down before the BI cluster size can be changed.• Information about BuffersFlushedatCheckpointHigh is stored in the OpenEdge Management Trend Database in the Db_ActBuf and Db_Checkpoint tables.

DB_BusyAIBufferWaitsHigh

Message	“After-image busy buffer waits are <i>n</i> . This is above the threshold. The current threshold is <i>x</i> .”
Description	Sent when database after-image busy buffer waits are above the defined threshold.
Type	Polled
Action	Raise AI block size.
Note	Information about BusyAIBufferWaitsHigh is stored in the OpenEdge Management Trend Database in the Db_ActLog table.

DB_BusyBIBufferWaitsHigh

Message	“Waits for busy before-image buffers is n . The current threshold is x .”
Description	Sent when the waits for busy before-image buffers percentage is above the threshold.
Type	Polled
Action	Verify that the BI block size is adequate.
Note	Information about BusyBIBufferWaitsHigh is stored in the OpenEdge Management Trend Database in the Db_ActLog table.

DB_CheckpointLengthShort

Message	“Checkpoint length is n seconds. The current threshold is x seconds.”
Description	Sent when the database checkpoint length is below the threshold.
Type	Polled
Action	Increase the BI cluster size.
Notes	<ul style="list-style-type: none">• If the database license is Workgroup, the BIW is disabled and cannot be enabled.• Information about CheckpointLengthShort is stored in the OpenEdge Management Trend Database in the Db_Checkpoint table.• The database must be down before the -BI clusters can be changed.

DB_DatabaseCommitsLow

Message	“Database commits are n . The current threshold is x .”
Description	Sent when database commits are below the threshold.
Type	Polled
Action	Make sure that adequate database activity has occurred for this sample.
Note	Information about DatabaseCommitsLow is stored in the OpenEdge Management Trend Database in the Db_ActSum table.

DB_DatabaseCrash

Message	“Database Broker, x , crashed!”
Description	Sent when the database broker crashes.
Type	Asynchronous

DB_DatabaseDown

Message	“Database Broker, x , is shutting down.”
Description	Sent when a database broker is shut down.
Type	Asynchronous
Note	This alert is informational only.

DB_EmptyAIBuffersWaitsHigh

Message	“After-image buffers unavailable are n . The current threshold is x .”
Description	Sent when there are no database after-image buffers available.
Type	Polled
Action	Increase the <code>-aibufs</code> startup parameter.
Note	Information about EmptyAIBuffersWaitsHigh is stored in the OpenEdge Management Trend Database in the Db_ActLog table.

DB_EmptyBIBufferWaitsHigh

Message	“Wait percentage for empty before-image buffers is $n\%$. The current threshold is x .”
Description	Sent when wait percentage for empty before-image buffers is above the threshold.
Type	Polled
Action	Increase the Before-image Buffers (<code>-bibufs</code>) startup parameter.
Note	Information about EmptyBIWaitsHigh is stored in the OpenEdge Management Trend Database in the Db_ActLog table.

DB_FathomTrendDatabase

Message	“The database at <i>database location</i> does not match the FathomTrendDatabase schema.”
Description	Sent when the database running at the port specified for the OpenEdge Management Trend Database in the Progress Explorer is not an OpenEdge Management Trend Database.
Type	Asynchronous
Action	Specify another port, or stop the database running at that port and start the OpenEdge Management Trend Database.

DB_NormalShutdown

Message	“A normal shutdown has occurred for database <i>x</i> .”
Description	Sent when normal database shutdown has completed.
Type	Asynchronous
Action	Check the database log file for additional information regarding the shutdown.

DB_PartialAIBufferWritesHigh

Message	“After-image partial write percentage is <i>n</i> %. The current threshold is <i>x</i> %.”
Description	Sent when the database after-image buffer partial writes are above the threshold.
Type	Polled
Action	Increase AI block size.
Note	Information about PartialAIBufferWritesHigh is stored in the OpenEdge Management Trend Database in the Db_ActLog table.

DB_PhysicalReadHigh

Message	“Database physical to logical read ratio is <i>n</i> . The current threshold is <i>x</i> .”
Description	Sent when the database physical-to-logical read ratio is above the threshold.
Type	Polled
Action	Increase database buffers (-B) startup parameter.
Note	Information about PhysicalReadHigh is stored in the OpenEdge Management Trend Database in the Db_ActBuf table.

DB_ReadsToRequestsHigh

Message	“Database reads to requests percentage is <i>n</i> . The current threshold is <i>x</i> .”
Description	Sent when the database Read to Request percentage is unusually high.
Type	Polled
Action	Review User Requests and User Reads to ensure proper ratios.
Note	Information about DatabaseReadstoRequestsHigh is stored in the OpenEdge Management Trend Database in the Db_ActSum table.

DB_RecordWaitsHigh

Message	“The percentage of waits for records is $n\%$. The current threshold is $x\%$. Exclusive= $a\%$. Share= $b\%$. Upgrade= $c\%$. RecGet= $d\%$.”
Description	Sent when waits for records are above the threshold.
Type	Polled
Action	Review what users hold share and exclusive locks by querying the _ActLock and _UserLock VSTs.
Note	Information about RecordWaitsHigh is stored in the OpenEdge Management Trend Database in the Db_ActRec table.

DB_ResourceAdded

Message	“Database Resource, x , added.”
Description	Sent when a managed database object is created.
Type	Asynchronous
Note	This alert is informational only.

DB_ResourceDisabled

Message	“Database Resource, x , disabled.”
Description	Sent when a database resource is disabled.
Type	Asynchronous
Note	This alert is informational only.

DB_ResourceEnabled

Message	“Database Resource, x , enabled.”
Description	Sent when a database resource is enabled.
Type	Asynchronous
Note	This alert is informational only.

DB_ResourceNameConflict

Message	“Cannot create database resource. A database resource with this name already exists.”
Description	Sent when you create a database configuration that has the same name as an existing OpenEdge Management database resource. As a result, OpenEdge Management could not create a database resource for the new database configuration.
Type	Asynchronous
Action	Be sure to give each OpenEdge Management resource a unique name.

DB_Startup

Message	“A startup has occurred for database <i>x</i> .”
Description	Sent when a database startup has been detected.
Type	Asynchronous

DB_TrendingStopped

Message	“Trending information has stopped being gathered for database <i>n</i> .”
Description	Sent when trending information has stopped being gathered for a database.
Type	Asynchronous
Action	Check the AdminServer log file (<code>admserv.log</code>) for additional information.
Note	The gathering of trending information stops when the database is shut down, the Db_agent is disconnected from the database, or the trending flag is turned off.

DB_UserCountHigh

Message	“The user count for the specified database has exceeded the threshold. Threshold: <i>x</i> , User Count: <i>y</i> .”
Description	Sent when the defined user count threshold is exceeded.
Type	Polled

DB_VariableAreaExtentGrow

Message	“Extent <i>ExtentName</i> has extended more than 3 times in this sample. The threshold is <i>x</i> .”
Description	Sent when a database variable-length data or before-image extent extends.
Type	Polled
Action	Add an additional fixed-length extent.
Note	Information about VariableAreaExtentGrow comes from the _ActIOFile VST.
See Also	<i>OpenEdge Data Management: Database Administration</i> for details about how to add an extent.

DiminishedFileGrowth

Message	“The file is growing slower than the specified rate.” file: + filename.
Description	Sent when the growth rate specified on the File Growth Rate rule has not been met.
Type	Polled

DiskAvgQueueHigh

Message	“Disk average queue length is <i>n</i> . The current threshold is <i>threshold</i> .”
Description	Sent to inform the user of the average number of processes in the queue for disk activity. This information can be reads or writes. However, it is typically expressed as reads.
Type	Polled
Action	Review the disk performance information, disk system layout, and application use of disk.

DiskBusyThresholdExceeded

Message	“Disk Busy Threshold Exceeded! Value: <i>x</i> , Threshold: <i>y</i> .”
Description	Sent when a disk’s configured threshold is exceeded.
Type	Polled
Action	<p>Consider the following options to reduce the disk’s load:</p> <ul style="list-style-type: none">• Spread databases across multiple disks which will increase the Blocks in database buffers (-B parameter).• Add more disks.• Request that your system administrator invest in faster disks.
Notes	<ul style="list-style-type: none">• Adding more disks to a system increases overall disk I/O because reads and writes can span across multiple disks. However, the performance results depend on how the multiple disks are grouped and how you structure your databases.• For information on how your OpenEdge databases affect disk I/O, view the following OpenEdge VSTs:<ul style="list-style-type: none">– <code>_ActBuffer._Buffer-OSRds</code> — Displays information about the number of database block reads from disk.– <code>_ActBuffer._Buffer-OSWrts</code> — Displays information about the number of database block writes to disk.– <code>_ActIOType</code> — Displays information about types of input/output activity, such as database reads and writes, BI and AI reads, total reads, BI and AI writes, and committed transactions.– <code>_ActIOFile</code> — Displays information about input/output activity, including the number of reads, writes, and extends for each file.

DiskNotFound

Message	“Cannot obtain information about the disk resource.”
Description	Sent when the disk monitor fails to obtain valid query information for the disk resource.
Type	Asynchronous
Action	<p>Because the disk monitor cannot locate the underlying disk resource, the disk monitor is unable to obtain information about the disk usage. This might be related to a problem with the disk itself or with the machine-specific library used to monitor the system resources.</p> <p>Check the AdminServer log file (<code>admserv.log</code>) to see if the osmetrics shared library has logged errors while initializing or during operation.</p>

ExcessiveFileGrowth

Message	“The file is growing faster than the specified rate.” file: + filename.
Description	Sent when the growth rate specified on the File Growth Rate rule has been exceeded.
Type	Polled

FathomTrendingUnavailable

Message	“Fathom cannot reach the trend database at <i>machine name:port number</i> . Check the log file for more information.”
Description	Sent when OpenEdge Management cannot reach the defined trend database at the specified HTTP port.
Type	Asynchronous
Action	Check the AdminServer log (admserv.log) file on the specified machine for more information. Use the information below in Notes for starting points.
Notes:	<p>This alert triggers if:</p> <ul style="list-style-type: none">• OpenEdge Management is not running on the trending database’s machine.• The specified location does not have a local trend database defined.• The trend database is not running at the specified location.• There is a communication problem between machines.

FileDoesNotExist

Message	“The file does not exist.”
Description	Sent when the file resource monitor cannot find the file specified as a file size resource.
Type	Polled
Action	Check the file size resource’s path. If the path is correct but the file is missing, restore the file from backup.

FileExists

Message	“The specified file exists. File: <i>x</i> .”
Description	Sent when a user specifies that a file monitor alert should be used to indicate that a file exists.
Type	Polled

FilesDirectory

Message	“The file specified is a directory.”
Description	Sent when the file specified for a file resource is a directory.
Type	Polled
Note	OpenEdge Management reports the size of a directory as zero-length. Because of this, the file resource monitor treats the directory’s status as passed, regardless of the type of comparison specified in the monitor’s rules.

FileModified

Message	“The file was modified.” file: <i>filename</i>
Description	Sent when the file has been modified and the File Modified rule has been configured.
Type	Polled

FileSizeEqual

Message	“The file size is equal to the specified size. Actual size: <i>x</i> , Specified Size: <i>x</i> .”
Description	Sent when the file size monitor detects that a file’s size is equal to its configured value.
Type	Polled
Action	Take necessary remedial actions to correct the file size.

FileSizeExceeded

Message	“The file size exceeded the specified size. Actual Size (bytes): <i>actual file size</i> , Specified Size (bytes): <i>specified file size</i> .”
Description	Sent when a file size monitor detects that the file exceeded its configured size.
Type	Polled
Action	Take any necessary actions to correct the file size, such as truncating the file.

FileSizeLow

Message	“The file size is less than the specified size. Actual Size: <i>x</i> , Specified Size: <i>y</i> .”
Description	Sent when the file size monitor detects that a file is less than its specified size.
Type	Polled
Action	Take necessary remedial actions to correct the file size.

FileSizeNotEqual

Message	“The file size does not equal the specified size. Actual Size: <i>x</i> , Specified Size: <i>y</i> .”
Description	Sent when a file size resource fails because its size does not equal its configured size.
Type	Polled
Action	Take necessary remedial actions to correct the file size.

FileStale

Message	“The file is older than the age specified. file: <i>filename</i> .”
Description	Sent when the file age specified by the File Age Rule has been exceeded.
Type	Polled

FileSystemNotFound

Message	“Cannot obtain information about the file system resource.”
Description	Sent when the file system monitor fails to obtain valid query information for the file system resource.
Type	Asynchronous
Action	<p>Because the file system monitor cannot locate the underlying file system resource, the file system monitor is unable to obtain information about file system usage. This might be related to a problem with the file system itself or with the machine-specific library used to monitor the system resources.</p> <p>Check the AdminServer log (admserv.log) to see if the osmetrics shared library has logged errors while initializing or during operation.</p>

FileSystemUsedThresholdExceeded

Message	“FileSystem Used Threshold Exceeded! Value: <i>x</i> , Threshold: <i>y</i> .”
Description	Sent when a file system’s configured threshold is exceeded.
Type	Polled
Action	Free up space on the file system by deleting unnecessary files; create a multivolume database, or update existing multivolume databases.
Notes	<ul style="list-style-type: none">• OpenEdge Management gathers file system information primarily for trend analysis. The FileSystemUsedThresholdExceeded alert can help you prevent trouble caused by lack of disk space.• The RDBMS VST _AreaStatus displays data about the status of areas. Use the information in the _AreaStatus VST, along with the file system information trended by OpenEdge Management, to predict when it is time to extend or redesign your database. Viewing the information in your database’s _AreaExtents record can also help track database file growth.

HTTPDownloadFailure

Message	“OpenEdge Management failed to retrieve the specified Web page. URL: <i>The URL of the page Fathom attempted to download</i> , HTTP Response Code: <i>The response code reported by the Web server</i> .”
Description	Sent when the OpenEdge Management cannot download the URL provided to an HTTP monitor.
Type	Polled
Action	The reason why the attempted download failed is given in the response code. Refer to RFC 2616 for information about specific values.

HTTPRedirect

Message	“The monitored page was redirected. Monitored URL: <i>the URL being monitored by Fathom</i> , Retrieved URL: <i>the URL actually downloaded by Fathom</i> .”
Description	Sent when the URL provided to an HTTP monitor is redirected to another location, and you have chosen to alert on this condition.
Type	Polled

InvalidProgressVersion

Message	“OpenEdge Management is bound to an unsupported Progress version or patch level. Current Progress Version: <i>version string</i> , Minimum Required Progress Version or Patch Level: <i>version string</i> .”
Description	Sent when OpenEdge Management detects that the OpenEdge version is unsupported or not at the right patch level.
Type	Asynchronous
Action	Update to the identified OpenEdge version or patch level.

JobStartFailure

Message	“Unable to execute the job as an action. Job: <i>x</i> .”
Description	Sent when a job that was specified as the alert action for a resource does not execute.
Type	Asynchronous
Action	Check the log file for additional information regarding the failure of the job.

LatchWaitCountHigh

Message	“Latch waits for latch <i>latchname</i> are <i>n</i> . The current threshold is <i>threshold</i> .”
Description	Sent when the number of latch counts is above the threshold.
Type	Polled
Action	Review which users are accessing and using the latches. Review the <code>-spin</code> setting for the database.
Note	These details reflect a per-latch basis. There are 31 latches for a database. There can be more than one latch for this rule, and each latch should be a separate rule that must be evaluated.

LogActionWriteError

Message	“There was a problem writing to the log file. Check that the directory exists and the file is writable. File: <i>the file to which the action is attempting to write</i> .”
Description	Sent if a log action cannot write to the indicated file.
Type	Asynchronous
Action	Check to make sure that the directory exists and that the file has write permissions.

LogFileIOException

Message	“The Log File Monitor could not open or write to the <i>name of log file being monitored</i> .”
Description	Sent when the log file monitor encounters an input/output exception with the file specified in the Filename Input parameter.
Type	Synchronous
Action	Check the file’s permissions to make sure that the AdminServer’s rights match the file’s rights; if they do not, the monitor will not be able to open it. Also check the directory’s permissions.
Note	OpenEdge Management generates this alert when the log file monitor has trouble opening the file or permissions problems. An interruption in I/O stream can also trigger this alert.

LogFileNotFound

Message	“ <i>Name of monitored file</i> was not found.”
Description	Sent when the log file monitor cannot find the file specified in the Filename Input parameter.
Type	Synchronous
Action	Make sure the file exists in the specified directory.
Note	This alert is generated only when the log file monitor cannot find the file, not when the file is found but cannot be opened.

MalformedPattern

Message	“The Log File Monitor could not understand the regular expression syntax given in one of its Search Criteria. <i>Pattern and name of Search Criteria in which the error occurred</i> .”
Description	Sent when the log file monitor encounters an error with the Search Text listed in its Search Criteria.
Type	Synchronous
Action	Make sure the syntax given in the Search Text field is valid Perl 5 regular expression syntax.
See Also	OpenEdge Management: Resource Monitoring Guide for details about valid Perl 5 regular expression syntax.

MalformedURL

Message	“The defined URL monitor has a malformed, or incorrect, URL in its definition. The URL should be changed to reflect a valid URL.”
Description	The URL for the HTTP resource is malformed.
Type	Polled

MemoryNotFound

Message	“Cannot obtain information about the memory resource.”
Description	Sent when the memory resource monitor fails to obtain valid query information for the memory resource.
Type	Asynchronous
Action	<p>Because the memory monitor cannot locate the underlying memory resource, the memory monitor is unable to obtain information about the memory usage. This might be related to a problem with one or more memory boards on the machine or with the machine-specific library used to monitor the system resources.</p> <p>Check the AdminServer log file (admserv.log) to see if the osmetrics shared library has logged errors while initializing or during operation.</p>

NetworkResourceFailure

Message	“The network resource failed to respond.”
Description	Sent when a network resource fails to respond.
Type	Asynchronous
Action	Verify that the service on the monitored machine is running.
Note	If the resource being monitored is a TCP or UDP port, this alert indicates only that the port cannot be accessed, not that the machine on which the port exists is unavailable. This alert is never generated for an ICMP monitor, as ICMP monitors do not use ports.

NetworkResourceTardy

Message	“The tardy threshold has been exceeded. A response time that is greater than the tardy threshold, but less than the timeout threshold will result in the resource status being reported as tardy.”
Description	Sent when the network resource response time exceeded the tardy threshold.
Type	Polled

NetworkResourceTimeout

Message	“The timeout threshold has been exceeded. Response: <i>resource response time</i> ms, Threshold: <i>timeout threshold</i> ms.”
Description	Sent when the network resource response time exceeded the timeout threshold.
Type	Polled

NetworkResourceUnreachable

Message	“The network resource is unreachable.”
Description	Sent when the network resource cannot be reached, such as after attempts to ping the resource were unsuccessful.
Type	Asynchronous
Action	Check the network connection on the machine you want to access, as well as the machine that OpenEdge Management is on. If the network connections appear fine, contact your network administrator.

NoContentInPage

Message	“The HTML page could not be searched because no content was retrieved.”
Description	Sent when the HTTP monitor could not download the Web page for the resource, presenting a situation for which there would be no content available to search.
Type	Polled

NoSearchCriteria

Message	“The Log File Monitor does not have any Search Criteria associated with it.”
Description	Sent when the log file monitor does not have any search criteria associated with it.
Type	Synchronous
Action	Edit the Log File Monitor, making sure to define search criteria.
Note	The Log File Monitor must have at least one search criterion associated with it.

NS_AbnormalShutdown

Message	“The NameServer shutdown abnormally. NameServer: <i>name</i> , Port: <i>port</i> .”
Description	The NameServer shut down abnormally.
Type	Asynchronous
Action	Examine the NameServer, broker, and AdminServer log files for any additional information to assist you in determining why the NameServer shut down in this manner.

NS_ApplicationServiceNotFound

Message	“Application Service requested by client not found. Application Service: <i>name</i> , Client host: <i>host</i> , Port: <i>port</i> .”
Description	Sent when there are no AppServers registered at the NameServer for the Application Service requested by a client.
Type	Asynchronous
Action	If the Application Service requested is valid, examine the NameServer and Broker log files to determine why a broker is not registered for the requested AppService.

NS_BrokerRegistrationFailure

Message	“The Broker registration failed. The named Application Service already has a Broker, and Load Balancing is not installed. Application Service: <i>appservice</i> . Broker: <i>name</i> , Host: <i>host</i> , Port: <i>port</i> , UUID: <i>uuid</i> .”
Description	The identified Broker was not registered for the requested Application Service. The named Application Service already has a broker registered for it, and the Load Balancing option is not installed.
Type	Asynchronous
Action	See if the broker’s list of supported Application Services conflicts with that of other brokers. Consider installing the load balancing option.

NS_BrokerTimeout

Message	“The registered broker is not responding. The broker will not be registered. Broker: <i>name</i> .”
Description	Sent when a registered broker is not responding.
Type	Asynchronous
Action	Examine the broker’s log file for any additional information to assist in determining why the broker is not responding.

NS_ClientRequestRejected

Message	“The client request was rejected due to an incorrect message header, or wrong version information in the client message. Client host: <i>name</i> , Port: <i>port</i> .”
Description	The NameServer received a request with bad header information. The header information was incorrect, or the protocol version field within the header contained an unsupported version identifier.
Type	Asynchronous
Action	Determine if the request came from a legitimate NameServer client. If the client is an OpenEdge-based client, ensure that the NameServer version is recent enough to support the version of the client.

NS_DuplicateBrokerUUID

Message	“Erroneous UUID received from a second broker. The UUID is already registered. Registered Broker: <i>brokername</i> , Host: <i>name</i> , Port: <i>port</i> . Secondary Broker: <i>brokername</i> , Host: <i>name</i> , Port: <i>port</i> , UUID: <i>uuid</i> .”
Description	Sent when a broker attempts to register with the NameServer using a UUID that has already been registered by another broker.
Type	Asynchronous
Action	Examine the <code>ubroker.properties</code> file for duplicated UUID specifications.

NS_NameServerReregisteredBroker

Message	“The NameServer has reregistered the broker for consistency. Broker: <i>name</i> , Host: <i>host</i> , Port: <i>port</i> , UUID: <i>uuid</i> .”
Description	The NameServer detected that the broker has been restarted without the NameServer receiving an unregistered request, or having timed out the broker. To ensure that the values associated with the broker are the latest values, the NameServer has unregistered and reregistered the broker.
Type	Asynchronous
Action	Determine how the broker is being shut down and why it is not sending an unregistered message to the NameServer. Consider if the timeout that the NameServer is using for the brokers is too long, preventing the NameServer from detecting that a broker is no longer responding.

NS_NormalShutdown

Message	“The NameServer shutdown normally. NameServer: <i>name</i> , Port: <i>port</i> .”
Description	The NameServer shut down normally.
Type	Asynchronous

NS_Startup

Message “The NameServer has been started. NameServer: *name*, Port: *port*.”

Description The NameServer has been started.

Type Asynchronous

PageContentChanged

Message “The hash code comparison failed on the content retrieved for the URL. URL: *The URL for which a hash comparison was made*.”

Description Sent if the hash code generated for downloaded Web page content did not match the baseline hash code created on the first poll. This indicates that content that should have been static has changed.

Type Polled

ProcessCPUBusyThresholdExceeded

Message “Process CPU Busy Threshold Exceeded! Value: *%s*, Threshold: *%s*.”

Description Sent when the percentage of CPU usage being consumed by this process exceeds the set threshold.

Type Polled

ProcessPhysicalMemoryThresholdExceeded

Message “Process Physical Memory Used Threshold Exceeded! Value: *%s*, Threshold: *%s*.”

Description Sent when the amount of physical memory being consumed by this process exceeds the set threshold.

Type Polled

ProcessVirtualMemoryThresholdExceeded

Message “Process Virtual Memory Used Threshold Exceeded! Value: *%s*, Threshold: *%s*.”

Description Sent when the amount of virtual memory being consumed by this process exceeds the set threshold.

Type Polled

ProjectCreated

Message	“Fathom project file not found, new project created.”
Description	Sent when OpenEdge Management starts and cannot find the OpenEdge Management project file (fathom.xml).
Type	Asynchronous

ProjectLoadFailed

Message	“Fathom project file could not be loaded. Project file renamed and new project created. Old project file: <i>filename</i> .”
Description	Sent when an existing OpenEdge Management project file cannot be loaded at OpenEdge Management start time. The existing OpenEdge Management project file is renamed and a default project file is created.
Type	Asynchronous

ProjectNoRead

Message	“Fathom project file cannot be read.”
Description	Sent when OpenEdge Management starts and cannot read the OpenEdge Management project file (fathom.xml).
Type	Asynchronous
Action	Check the protections on fathom.xml to make sure Read access is available.

ProjectUpgraded

Message	“Fathom project file upgraded for compatibility with current Fathom version.”
Description	The OpenEdge Management project file was created with an earlier version of OpenEdge Management, and the file has been upgraded for use with the current version of OpenEdge Management. The file is no longer usable by earlier versions of OpenEdge Management.
Type	Asynchronous

ProjectVersionLater

Message	“Fathom project file version is later than the current Fathom version.”
Description	Sent when an attempt has been made to load an OpenEdge Management project file (fathom.xml) created with a newer version of OpenEdge Management, and the file cannot be loaded by the current version of OpenEdge Management.
Type	Asynchronous

ReportRunFailed

This section identifies the specific message-related text that can display indicating a report run has failed. Scan the messages presented in this section to find the one matching the message you received.



To obtain more details related to a report instance for which any ReportRunFailed alert displays:

1. Select **Reports**→ **Defined Reports**.
2. Select the report instance name in the list frame and display the report definition in the edit mode in the detail frame.
3. Select the **Generate debug log file** option, resubmit, and rerun the report. It is possible that more log files will display. You can use this data to further investigate your problem.

For more information about reports, see the [OpenEdge Management: Reporting Guide](#).

Message	“Output directory not created: <output directory>.”
Description	The report engine could not create the necessary directories to store the report output. Check the file system for privileges.
Action	Check the file system for privileges.

Message	“4GL execution error, exit code <return code>. See log files.”
Description	The report did not run to completion because of an ABL issue. See the Report Output file (report.out) and the AdminServer log file (admserv.log) for more information.
Action	See the report output log files.

Message	“Graphing request xml file does not exist.”
Description	The report failed to complete because there was a problem creating a graph for the report. The _graph.xml file is missing from the report output.
Action	See the log files.

Message “Report output xml does not exist.”

Description The report failed to complete because the `_data.xml` file was not created.

Action See the log files.

Message “Error writing output file for report. See log files.”

Description There was an I/O error when generating the output file for the report.

Action See the log files.

Message “Transformation error. See log files.”

Description The report engine uses XSLT to create the various output formats from the `_data.xml`. There was an error transforming the XML file to one of the desired output formats.

Action See the log files.

Message “Transformation error for HTML output. See log files.”

Description There was an error transforming the data XML file into HTML output using XSLT.

Action See the log files.

Message “Transformation error for text output. See log files.”

Description There was an error using XSLT to transform the data XML file into text output.

Action See the log files.

Message “SAX parsing error. See log files.”

Description The report failed due to an error parsing an XML file. See the Report Output file (`report.out`) and the AdminServer log file (`admserv.log`) for more information.

Action See the Report Output file (`report.out`) and AdminServer log file (`admserv.log`) for more information.

Message	“Graphing error. See log files.”
Description	The report failed because the graphing engine had an error producing a graph for the report. See the report output and AdminServer log files (<code>admserv.log</code>) for more information regarding the error.
Type	Asynchronous
Action	See the Report Output file (<code>report.out</code>) and AdminServer log file (<code>admserv.log</code>).

Message	“XSL stylesheet not found: <code><filename></code> .”
Description	The report failed because it could not find the specified XSL stylesheet to use in transforming the data XML to another output form.
Action	Ensure that the stylesheet is available in the following subdirectory location: <code><OpenEdgeManagement-install-dir>/web/report/xsl</code> .

Message	“Report transformation ran out of memory.”
Description	The reports use XSL transformations to generate the HTML and text output formats from the XML output that ABL creates. The XML file was too large for the report engine to transform the file, thus the engine ran out of memory. If the report period and/or report format was modified so there is less data in the XML file, the report output will be smaller and the engine will more likely be able to process the file in the amount of memory allotted.
Action	Try reducing the number of columns or rows in the report output by changing the report period or report format.

ResrcDoesNotExist

Message	“The referenced resource, <code>x</code> , does not exist and is referenced by <code>x</code> .”
Description	The project file contains a reference to a resource that does not exist.
Type	Asynchronous

RunQueueHigh

Message	“Run queue for CPU is <code>n</code> . The current threshold is <i>threshold</i> .”
Description	Sent to identify the number of processes waiting to use the CPU.
Type	Polled
Action	Review what processes are using the CPU. Verify that there is not a runaway process on the system.

SearchPatternFound

Message	“The search pattern was found in the Web page.”
Description	Sent if the HTTP monitor located the specified pattern in the downloaded Web page and you have chosen to receive alerts when the pattern is found.
Type	Polled

SearchPatternNotFound

Message	“The search pattern was not found in the Web page.”
Description	Sent if the HTTP monitor could not locate the specified pattern in the downloaded Web page and you have chosen to receive alerts when the pattern is not found.
Type	Polled

SystemMemoryUsedThresholdExceeded

Message	“System Memory Used Threshold Exceeded! Value: <i>x</i> , Threshold: <i>y</i> .”
Description	Sent when the system memory’s configured threshold is exceeded.
Type	Polled
Action	Reduce memory usage by reducing the number of running processes. If necessary, request additional memory from your system administrator.

TaskInQueueFailure

Message	“Unable to schedule task <i>x</i> , already in work queue, exception message <i>y</i> .”
Description	Sent when an instance of a report or job is already running when OpenEdge Management attempts to schedule it.
Type	Asynchronous

TaskExecFailure

Message	“Call to <code>tskExec.exec</code> failed for task: <i>x</i> .”
Description	Sent when OpenEdge Management encounters a failure when trying to access the OpenEdge Management Trend Database resource.
Type	Asynchronous

TaskLocalDBAssocError

Message	“Unable to associate local FathomTrendDatabase with <i>task type: task name.</i> ”
Description	Sent when OpenEdge Management encounters a failure when trying to access the local OpenEdge Management Trend Database resource.
Type	Asynchronous

TaskQueueFull

Message	“Unable to schedule task because the work queue is full. Task: <i>taskname</i> . Exception message: <i>exceptionmsg.</i> ”
Description	OpenEdge Management encountered a failure when it attempted to schedule a job or report to run; the work queue is full.
Type	Asynchronous

TaskRemoteDBAssocError

Message	“Unable to associate remote FathomTrendDatabase with <i>task type: task name.</i> ”
Description	Sent when OpenEdge Management encounters a failure when trying to access the remote OpenEdge Management Trend Database resource.
Type	Asynchronous

TaskRunError

Message	“Failed to run task <i>x</i> , exception message <i>y.</i> ”
Description	Sent when OpenEdge Management encounters a failure when trying to run a job or report.
Type	Asynchronous

TaskStderrListenerFailed

Message	“Unexpected exception starting stderr listener thread in task <i>x</i> , exception message <i>y.</i> ”
Description	Sent when a job, configured to throw an alert if its execution exceeds a predefined time period, does not finish before the timer expires.
Type	Asynchronous

TaskStdinReadFailed

Message	“Unexpected exception reading input from task <i>x</i> , exception message <i>y</i> .”
Description	Sent when OpenEdge Management failed to read the output of a job or report.
Type	Asynchronous

TaskWaitFailure

Message	“Unexpected exception waiting for task <i>x</i> to complete, exception message <i>y</i> .”
Description	Sent when OpenEdge Management encounters a failure when waiting for a job or report to complete.
Type	Asynchronous

TemplateNotLoaded

Message	“Error occurred loading one or more Fathom template files. Not all default resources have been created. See the Fathom log file for detailed information on the import actions that were attempted.”
Description	<p>When OpenEdge Management creates a new project file or upgrades an existing project to the latest revision level, it populates the project with a set of default resources. These resources are imported from the templates in the OpenEdge Management template directory.</p> <p>This error indicates that one or more template files were not imported. Check the AdminServer log file (<code>admserv.log</code>) for more information. The OpenEdge Management import facility can be used interactively to import template files.</p>
Type	Asynchronous
Action	Check the AdminServer log file (<code>admserv.log</code>) for more information. Note that you can use the Import facility interactively to import template files. See the sections on importing and exporting in the <i>OpenEdge Management: Resource Monitoring Guide</i> .

TimerExpired

Message	“ <i>job name</i> failed to complete in <i>timeunits</i> : <i>timescale</i> .”
Description	Sent when a job has been configured to throw an alert if its execution exceeds a predefined time period (in minutes or hours), and the timer has expired before the job finished.
Type	Polled

VirtualMemoryUsedThresholdExceeded

Message	“Virtual Memory Used Threshold Exceeded! Value: <i>x</i> , Threshold: <i>y</i> .”
Description	Sent when the virtual memory’s configured threshold for memory used is exceeded.
Type	Polled
Action	Reduce memory usage by reducing the number of running processes. If necessary, request additional memory from your system administrator.
Note	View the OpenEdge VST _Startup, as it displays information about startup parameters that influence initial memory consumption. Values for AI Buffers, BI Buffers, Buffer Cache, and Lock Table size are related to shared memory.

WS_AgentAdded

Message	“WebSpeed broker added agent(s). Broker: <i>name</i> , Number of agents added: <i>num</i> .”
Description	Sent when the WebSpeed agents have been added to the pool of available agents.
Type	Asynchronous

WS_AgentKilled

Message	One of two messages can display for this alert: <ul style="list-style-type: none">• “Agent killed. Agent PID: <i>PID</i>.”• “Agent cannot be killed at this time. Agent PID: <i>PID</i>.”
Description	Sent when a user manually destroys an agent or agents. Typically a user initiates an agent kill action when agents hang under a connecting status for a long time.
Action	If the kill request cannot be processed, check the log file.
Type	Asynchronous
See Also	OpenEdge Management: Servers Guide

WS_AgentTrimmed

Message	“WebSpeed broker trimmed agent(s). Broker: <i>name</i> , Number of agents trimmed: <i>num</i> .”
Description	Sent when WebSpeed agents have been trimmed from the pool of available agents.
Type	Asynchronous
See Also	OpenEdge Management: Servers Guide

WS_AgentUnavailable

Message	“Agent has been unavailable state for more than the specified number of polls. Threshold: <i>threshold</i> , Number of polls: <i>number of polls</i> , PID: <i>process ID</i> .”
Description	Sent when an agent has been unavailable for more than the specified number of polls.
Type	Polled
Action	Check the AdminServer log file (admserv.log) for further information about AgentUnavailableTimeout.

WS_AverageProcedureDurationHigh

Message	“The average execution time of a procedure has exceeded the threshold. Threshold: <i>threshold</i> Current Value: <i>Current value</i> Procedure: <i>Procedure name</i> .”
Description	The average time spent executing a procedure during the polling interval exceeded the threshold. This situation could indicate a bottleneck in the application or other unforeseen events that inhibit the offending procedure from executing as quickly as expected.
Type	Polled
See Also	OpenEdge Management: Servers Guide

WS_BrokerAbnormalShutdown

Message	“WebSpeed broker shut down abnormally. Broker: <i>name</i> .”
Description	Sent when a WebSpeed broker shut down abnormally (crashed).
Type	Asynchronous
Action	View the appropriate log file for further information.

WS_BrokerNormalShutdown

Message	“WebSpeed broker shutdown normally. Broker: <i>name</i> .”
Description	Sent when a WebSpeed broker shuts down normally.
Type	Asynchronous

WS_BrokerStartup

Message	“WebSpeed broker shutdown normally. Broker: <i>name</i> .”
Description	Sent when a WebSpeed broker starts up.
Type	Asynchronous

WS_NameServerUnavailable

Message	“WebSpeed broker failed to reach the NameServer. Broker: <i>name</i> , NameServer: <i>Nsname</i> .”
Description	Sent when a WebSpeed broker failed to contact the NameServer.
Type	Asynchronous
Action	Check the AdminServer log file (admserv.log) for more information about NameServer unavailable.

WS_QueuedRequestPercentHigh

Message	“The percent of queued requests has exceeded the threshold. Current Value: <i>value</i> , Threshold: <i>threshold</i> , Broker: <i>brokername</i> .”
Description	The percentage of requests queued during the polling interval exceeded the threshold. This situation could indicate bottlenecks or other unforeseen events that are slowing down request processing.
Action	Check the AdminServer log file (admserv.log) for more information about Request Queue Depth High.
Type	Polled
See Also	OpenEdge Management: Servers Guide

WS_RejectedRequestPercentHigh

Message	“The percentage of rejected requests has exceeded the threshold. Current Value: <i>Current value</i> Threshold: <i>threshold</i> .”
Description	The percentage of client requests rejected during the polling interval exceeded the threshold. This situation could indicate bottlenecks or tuning problems that prevent client requests from being serviced.
Type	Polled
See Also	OpenEdge Management: Servers Guide

Index

A

Actions

- and resource monitoring plan requirements 1–2
- relationship to alerts 1–3, 2–14

Alert details Summary page 2–13

Alert list

- command options 2–36
- details 2–37
- examples 2–38, 2–39

Alert properties

- Clear alert after 2–5
- Severity 2–5
- Throw alert after 2–5

Alerts

- See also* Asynchronous alerts
- See also* OpenEdge Management internal alerts
- See also* Polled alerts
- additional information in the OpenEdge Management documentation set 1–8, 2–4
- alert-related viewlets
 - Alert severity legend viewlet 2–16
 - Collection members viewlet 2–16
 - Resources with alerts viewlet 2–15
- and resource monitoring plan requirements 1–2
- assigning alert severity 2–6
- clearing
 - from the command line 2–30
 - in bulk 2–23
 - individual alerts 2–22

commands 2–33

configuring 2–4

data displayed in

- Alert details Summary page 2–13
- collection pages 2–15
- detail frame 2–13
- list frame 2–11
- main menu bar 2–11
- ToolTips 2–11

default and override hierarchy (graphic) 2–2

defined 1–2

defining an action for 1–3, 2–10

disabling 2–24, 2–28

in monitoring plans 2–25

noise 2–6

Occurrence count field 1–7, 2–14

OpenEdge Management internal alerts 2–39

options and default values

- additional information 2–4
- on the OpenEdge Management Configuration page 2–3
- on the Resource Monitor Defaults pages 2–3
- on the Resource Monitoring Plan pages 2–3
- See also* Monitoring plan settings

properties

- Clear alert after 2–5
- Severity 2–5
- Throw alert after 2–5, 2–6
- relationship to actions 1–2
- relationship to rules 1–2
- types of 1–3
- viewing 2–10

Alerts reference 3–1

- Asynchronous alerts 1–6
 - Always throw new alert field 1–7
 - defined 1–6
 - example 1–7
 - fields in the Rule definition section 1–7

C

- Clear alert after 2–5
- Clearing alerts
 - in bulk 2–23
 - in the command line 2–30
 - individual alerts 2–22
- Command-line interface
 - alert commands 2–33
 - clearing alerts 2–30
 - querying OpenEdge Management 2–29
 - starting and stopping OpenEdge Management 2–29
 - using the environment window 2–29
- Commands
 - alertlist 2–34, 2–36
 - additional options 2–36
 - group selection options 2–34
 - firealert 2–33
 - fully qualified resource key 2–36
- Configuration Advisor
 - setting threshold values 2–5
- Customized Viewlet icon 2–17

D

- Disabling alerts 2–24
 - for all OpenEdge Management resources 2–28
 - for an individual resource monitor 2–27
 - in monitoring plans 2–25

E

- Environment window 2–29

I

- Internal alerts *See* OpenEdge Management internal alerts

M

- Monitoring plan settings
 - alert options and default capabilities 2–2, 2–3

N

- Noise 2–6

O

- Occurrence count field 1–7, 2–14
- OpenEdge Management internal alerts 2–39
 - defining an action for all internal alerts 2–39
 - reviewing and processing internal alert data 2–40

P

- Polled alerts 1–4
 - defined 1–4
 - example 1–5
 - factors associated with 1–4
 - fields in the Rules definition section 1–6
- Polling interval
 - defined 1–3
 - field 1–5

R

- Rules
 - and resource monitoring plan requirements 1–2
 - configuring for individual resources 2–4
 - relationship to alerts 1–2

S

- Schedules
 - and resource monitoring plan requirements 1–2
 - relationship to rules 1–3
- Severity 2–5

T

Threshold values
 setting 2-4
 options to set 2-5

Throw alert after 2-5

ToolTips 2-11

V

Viewing alert details
 in e-mails 2-18
 in OpenEdge Management log file 2-20
 in OpenEdge Management reports 2-19

in OpenEdge Management Trend
 Database 2-21
in the detail frame 2-13
in the list frame 2-11
on collection pages 2-15
on the Alert details Summary page 2-13
on the main menu bar 2-11
on the Resource Monitoring Summary
 page 2-18
ToolTips 2-11

W

Web server port
 command-line interface 2-29

