



LoadMaster for Azure

Installation Guide

UPDATED: 27 July 2023

© 2022 Progress Software Corporation and/or one of its subsidiaries or affiliates. All rights reserved.

These materials and all Progress® software products are copyrighted and all rights are reserved by Progress Software Corporation. The information in these materials is subject to change without notice, and Progress Software Corporation assumes no responsibility for any errors that may appear therein. The references in these materials to specific platforms supported are subject to change.

#1 Load Balancer in Price/Performance, 360 Central, 360 Vision, Chef, Chef (and design), Chef Habitat, Chef Infra, Code Can (and design), Compliance at Velocity, Corticon, Corticon.js, DataDirect (and design), DataDirect Cloud, DataDirect Connect, DataDirect Connect64, DataDirect XML Converters, DataDirect XQuery, DataRPM, Defrag This, Deliver More Than Expected, DevReach (and design), Driving Network Visibility, Flowmon, Inspec, Ipswitch, iMacros, K (stylized), Kemp, Kemp (and design), Kendo UI, Kinvey, LoadMaster, MessageWay, MOVEit, NativeChat, OpenEdge, Powered by Chef, Powered by Progress, Progress, Progress Software Developers Network, SequeLink, Sitefinity (and Design), Sitefinity, Sitefinity (and design), Sitefinity Insight, SpeedScript, Stylized Design (Arrow/3D Box logo), Stylized Design (C Chef logo), Stylized Design of Samurai, TeamPulse, Telerik, Telerik (and design), Test Studio, WebSpeed, WhatsConfigured, WhatsConnected, WhatsUp, and WS_FTP are registered trademarks of Progress Software Corporation or one of its affiliates or subsidiaries in the U.S. and/or other countries.

Analytics360, AppServer, BusinessEdge, Chef Automate, Chef Compliance, Chef Desktop, Chef Workstation, Corticon Rules, Data Access, DataDirect Autonomous REST Connector, DataDirect Spy, DevCraft, Fiddler, Fiddler Classic, Fiddler Everywhere, Fiddler Jam, FiddlerCap, FiddlerCore, FiddlerScript, Hybrid Data Pipeline, iMail, InstaRelinker, JustAssembly, JustDecompile, JustMock, KendoReact, OpenAccess, PASOE, Pro2, ProDataSet, Progress Results, Progress Software, ProVision, PSE Pro, Push Jobs, SafeSpaceVR, Sitefinity Cloud, Sitefinity CMS, Sitefinity Digital Experience Cloud, Sitefinity Feather, Sitefinity Thunder, SmartBrowser, SmartComponent, SmartDataBrowser, SmartDataObjects, SmartDataView, SmartDialog, SmartFolder, SmartFrame, SmartObjects, SmartPanel, SmartQuery, SmartViewer, SmartWindow, Supermarket, SupportLink, Unite UX, and WebClient are trademarks or service marks of Progress Software Corporation and/or its subsidiaries or affiliates in the U.S. and other countries. Java is a registered trademark of Oracle and/or its affiliates. Any other marks contained herein may be trademarks of their respective owners.

Please refer to the NOTICE.txt or Release Notes – Third-Party Acknowledgements file applicable to a particular Progress product/hosted service offering release for any related required third-party acknowledgements.

Table of Contents

1 Introduction	4
1.1 Load Balancing in Microsoft Azure	4
1.2 Known Issues/Limitations	7
2 Installation Prerequisites	8
3 Creating a LoadMaster for Azure VM	9
3.1 Create an SSH Key Pair	9
3.2 Licensing Options	12
3.3 Creating a LoadMaster for Azure VM	13
3.3.1 Enable a 10 Gb Interface	22
3.3.1.0.1 Add a Single Interface to the LoadMaster	22
3.3.1.0.2 Add Multiple Interfaces to the LoadMaster	23
3.3.2 Recommended Pricing Tier	25
3.4 Licensing and Initial Configuration	26
4 Creating Virtual Services	28
5 Deploying a LoadMaster Programmatically	30
References	32
Last Updated Date	33


1 Introduction

This document provides step-by-step instructions on how to deploy a Kemp Virtual LoadMaster using the Azure Resource Manager (ARM) portal. This document is intended to provide an overview of LoadMaster for Azure and to introduce some basic aspects of LoadMaster functionality.

1.1 Load Balancing in Microsoft Azure

Before we create a LoadMaster Virtual Machine (VM) in Azure, it is important to understand the traffic flow so that VMs in Microsoft Azure can be configured appropriately.

Microsoft Azure Infrastructure as a Service (IaaS) deployments accept traffic only on published endpoints. Any request to access Microsoft Azure workloads passes through the default load balancing layer of the Microsoft Azure platform. The figure below depicts the default deployment without the use of a Kemp LoadMaster in Azure .



Any workload being published consists of an availability set, which represents a single VM or multiple VMs. When a VM is created, if an availability set exists, you have an option to connect the VM to an existing availability set. As more VMs are connected to an existing VM (and thus to an existing availability set), the built-in Microsoft Azure load balancer distributes connections when creating a load-balanced endpoint.


If you wish to use LoadMaster for Azure for your deployment, the following steps must be completed:

1. The LoadMaster for Azure needs to be deployed first.
2. All the VMs that need to be load balanced using the LoadMaster can then be created and must be connected to the existing LoadMaster VM to create the required grouping.

1 Introduction

3. Finally, when creating endpoints, we cannot use the **Load-Balance traffic on an existing endpoint** option in Azure as we do not want to use the Microsoft Azure Load Balancer to load balance incoming connections.

The figure below depicts the flow when LoadMaster for Azure is deployed:



Notice that VM1, VM2 and VM3 in this example are grouped into a single availability set and the endpoint for published Virtual Services is created only on the LoadMaster VM. By doing this, we receive all load balanced traffic on the LoadMaster VM and the logic of load balancing incoming connections are applied as per the configured Virtual Service on the LoadMaster for a given workload.

Also, notice that VM1, VM2 and VM3 will not have any endpoints as they are not going to be published directly to the internet.

There may be exceptions to this rule for connections that require direct connectivity to the VM such as Remote Desktop Connections to Windows Server OS.

1.2 Known Issues/Limitations

There are a couple of known issues/limitations to be aware of:

- Transparency is not possible in HA setups in Azure environments. For more information and requirements, refer to the **Transparency Feature Description** document on the [Kemp Documentation page](#).
- Do not downgrade from firmware version 7.2.36 or higher to a version below 7.2.36. If you do this, the LoadMaster becomes inaccessible and you cannot recover it.
- The Virtual Service IP address must be the same IP address as the network interface.
- Alternate default gateway support is not permitted in a cloud environment.

2 Installation Prerequisites

To support LoadMaster for Azure, the following are required:

- An active subscription of Microsoft Azure Virtual Machines
- A client computer running Windows 7 or newer
- Internet Explorer 9 or newer, or any modern browser
- A minimum of 2GB RAM on the cloud environment
- If you want to enable 10 Gb throughput for a LoadMaster virtual machine (VM) in Azure, you must select an Azure VM instance type that supports the 10 Gb Mellanox driver. Refer to the [Sizes for Linux virtual machines in Azure](#) page for further details.

It is not possible to bond interfaces on Azure LoadMasters.

3 Creating a LoadMaster for Azure VM

Please ensure that the prerequisites documented in the earlier section are met.


3.1 Create an SSH Key Pair

When creating a LoadMaster for Azure VM, there are two options for authentication - a password or an SSH public key. Kemp recommends using a password, but either way will work fine. If you choose to use a password, this section can be skipped and you can move on to the **Licensing Options** section to create the LoadMaster for Azure VM. If you choose to use an SSH public key, an SSH key pair will need to be created.

To create an SSH key pair, you will need to use a program such as the **PuTTYgen** or **OpenSSH**. As an example for this document, the steps in **PuTTYgen** are below:


1. Open PuTTYgen.

3 Creating a LoadMaster for Azure VM



2. Click **Generate**.

3 Creating a LoadMaster for Azure VM



3. Move the mouse over the blank area in the middle. This generates a random pattern that is used to generate the key pair.



4. Copy and save the public and private key as needed.

It is recommended to store SSH keys in a secure location.

3.2 Licensing Options

There are two main licensing options when deploying a LoadMaster for Azure:

- Hourly consumption
- Bring Your Own License (BYOL)


To use the BYOL option, follow the steps below:

1. Deploy the **BYOL – Trial and perpetual license** version of the Virtual LoadMaster (follow the steps in the section below to do this).
2. Contact a Kemp representative to get a license.

3. Update the license on your LoadMaster to apply the license change (**System Configuration > System Administration > Update License**).
4. Kemp recommends rebooting after updating the license.

3.3 Creating a LoadMaster for Azure VM

This section provides step-by-step instructions on how to deploy a Kemp Virtual LoadMaster in the ARM dashboard.



There is a new button on the Microsoft Azure portal called "**GET IT NOW**". When you click this button and log in, you are brought to the marketplace and a choice of products is displayed. When you select a product and click **Continue**, you are brought to the dashboard screen to create a Virtual Machine. Continue from the [Create step](#) below.

The steps in this document reflect the steps in the Azure Marketplace (<http://portal.azure.com>).


The steps below are carried out from <http://portal.azure.com> and not from <http://manage.windowsazure.com>.

To deploy a new LoadMaster using ARM, follow the steps below:

3 Creating a LoadMaster for Azure VM








1. From the Azure Management Portal dashboard, click **Marketplace**.



2. In the menu on the left, click the **New** icon.

3 Creating a LoadMaster for Azure VM

Results

NAME	PUBLISHER	CATEGORY
 2 Gbps Load Balancer (Hourly)	KEMP Technologies Inc	Azure Certified
 20 Mbps Load Balancer (BYOL and Free)	KEMP Technologies Inc	Azure Certified
 10 Gbps Load Balancer (Hourly)	KEMP Technologies Inc	Azure Certified
 200 Mbps Load Balancer (Hourly)	KEMP Technologies Inc	Azure Certified
 5 Gbps Load Balancer (Hourly)	KEMP Technologies Inc	Azure Certified

3. Enter **Kemp** in the search bar.
4. Click the desired Virtual Machine type.

If you want to enable 10 Gb throughput for a LoadMaster virtual machine (VM) in Azure, you must select an Azure VM instance type that supports the 10 Gb Mellanox driver. For more information, refer to the **Enable a 10 Gb Interface** section.

Select a deployment model ⓘ

Resource Manager
 ▼

Create

5. Select **Resource Manager** in the drop-down list and click **Create**.

If deploying a Bring Your Own License (BYOL) LoadMaster it is also possible to choose the classic deployment model. The remaining steps may vary slightly if using the classic deployment model.

*

Name

ExampleLoadMaster

✓

*

User name

bal

✓

*

Authentication type

Password

SSH public key

*

Password

.....

✓

Subscription

KEMPCorp

▼

*

Resource group

AA-TestWeb

▼

Location

East US

▼

OK

6. Enter a **Name** for the Virtual Machine.
7. Enter a **User name**.
 - a) This will not be used by LoadMaster for Azure. Provide a name of your choice. The default username to access the LoadMaster is **bal**.

b) Fill out the authentication details. There are two possible methods of authentication - using a password or an SSH key. Depending on what you select, complete the relevant step below:

- **Password:** Enter a password.

This password is used to access the LoadMaster WUI.

- **SSH Public Key:** Paste the SSH public key which was created in the **Create an SSH Key Pair** section. The private key is needed to connect to the LoadMaster using SSH.

It is recommended to store SSH keys in a secure location.

8. Select the relevant **Subscription**.
9. Select the relevant **Resource group**, or create one if needed.
10. Select the relevant **Location**.
11. Click **OK**.


★ Recommended View all		
A1 Standard ★	A3 Standard ★	A5 Standard ★
1 Core	4 Cores	2 Cores
1.75 GB	7 GB	14 GB
2 Data disks	8 Data disks	4 Data disks
2x500 Max IOPS	8x500 Max IOPS	4x500 Max IOPS
Load balancing	Load balancing	Load balancing
Auto scale	Auto scale	Auto scale
44.64 USD/MONTH (ESTIMATED)	178.56 USD/MONTH (ESTIMATED)	186.00 USD/MONTH (ESTIMATED)

Available sizes may change depending on the region.

3 Creating a LoadMaster for Azure VM

12. Select from the recommended pricing tiers. Click **View all** if the recommended pricing tier is not meeting the recommended requirements (see the table in the **Recommended Pricing Tier** section for further information regarding recommended pricing tiers).

13. Click **Select**.



The screenshot shows a configuration dialog box for an Azure VM. It has several sections: 'Storage' with a 'Disk type' dropdown set to 'Standard' (with 'Premium (SSD)' also visible); 'Storage account' set to 'lmarmtest1949'; 'Network' with 'Virtual network' set to 'LM-ARMTTest', 'Subnet' set to 'default (10.7.0.0/24)', 'Public IP address' set to '(new) ExampleLoadMaster', and 'Network security group' set to '(new) ExampleLoadMaster' (this row is highlighted in light blue); 'Extensions' set to 'No extensions'; and 'Monitoring' which is currently collapsed. An 'OK' button is at the bottom.

14. Select the relevant **Disk type**.

15. Select the relevant **Storage account**, or create one if needed.


16. Select the relevant **Virtual network**, or create one if needed.

17. Select the relevant **Subnet**.
18. Select the relevant **Public IP address**, or create one if needed.
19. Select the relevant **Network security group**, or create one if needed.

The security group should contain rules for port 8443 (management), 22 (SSH) and any other ports that are needed by the backend.

Do not block port 6973.

20. Select **Disabled** for **Diagnostics**.
21. Click **OK**.

 Validation passed

Basics

Subscription	KEMPCorp
Resource group	AA-TestWeb
Location	East US



Settings


Computer name	ExampleLoadMaster
User name	bal
Size	Standard A1
Disk type	Standard
Storage account	lmarmtest1949
Virtual network	LM-ARMTTest
Subnet	default (10.7.0.0/24)
Public IP address	(new) ExampleLoadMaster
Network security group	(new) ExampleLoadMaster
Availability set	None
Diagnostics	Disabled


OK

22. A summary of the settings is displayed. Click **OK**.

Offer details

LoadMaster Load Balancer ADC Content Switch by KEMP Technologies Inc Terms of use privacy policy	0.0000 USD/hr	
Standard A1 by Microsoft Terms of use privacy policy	0.0600 USD/hr Pricing for other VM sizes	


Marketplace purchases will be billed separately
 You cannot use your Azure monetary commitment funds or subscription credits for these purchases. You will be billed separately for marketplace purchases.


Azure resource
 You may use your Azure monetary commitment funds or subscription credits for these purchases. Prices presented are retail prices and may not reflect discounts associated with your subscription.

Terms of use

By clicking "Purchase", I (a) agree to the legal terms and privacy statement(s) associated with each Marketplace offering above, (b) authorize Microsoft to charge or bill my current payment method for the fees associated with my use of the offering(s), including applicable taxes, with the same billing frequency as my Azure subscription, until I discontinue use of the offering(s), and (c) agree that Microsoft may share my contact information and transaction details with the seller(s) of the offering(s). Microsoft does not provide rights for third-party products or services. See the [Azure Marketplace Terms](#) for additional terms.

Purchase

23. Click **Purchase**.

The creation of a VM may take a few minutes or more depending on the Azure portal's responsiveness and other factors. Ensure that the VM is created without any errors. Resolve any errors if needed.

When creating connected VMs, ensure to select the same **Virtual network** as the LoadMaster.

3.3.1 Enable a 10 Gb Interface

Follow one of the two procedures below depending on whether you are adding a single network interface or multiple network interfaces to the LoadMaster.

To enable 10 Gb throughput for a LoadMaster virtual machine (VM) in Azure, you must select an Azure VM instance type that supports the 10 Gb Mellanox driver. Accelerated Networking is supported on most general purpose and compute-optimized instance sizes with two or more vCPUs. These supported series are: D/DSv2 and F/Fs. On instances that support hyperthreading, Accelerated Networking is supported on VM instances with four or more vCPUs. Supported series are: D/Dsv3, E/Esv3, Fsv2, Lsv2, Ms/Mms and Ms/Mmsv2. Refer to the [Sizes for Linux virtual machines in Azure](#) page for further details.

3.3.1.0.1 Add a Single Interface to the LoadMaster

To enable 10 Gb interfaces on the LoadMaster, perform the following steps:

1. Deploy the LoadMaster.

For the purposes of this document, the Standard DSv2 machine size is used.

When you instantiate a 10 Gb interface, it appears as two interfaces in the LoadMaster Web User Interface (WUI). The two interfaces are related and have the same MAC address. Only the first interface has an IP address. If you want to modify the interface, you must do this on the interface that has the IP address listed.

2. License the LoadMaster.
3. Verify that the Mellanox driver has instantiated correctly by performing the following steps:
 - a) If the LoadMaster was deployed with a single interface, two interfaces are displayed under **System Configuration > Interfaces** on the LoadMaster WUI. If only one interface is displayed this means that the Mellanox driver has not instantiated.
 - b) To instantiate the Mellanox driver, you must shut down the LoadMaster. Navigate to: **System Configuration > System Administration > System Reboot**

3 Creating a LoadMaster for Azure VM

and click **Shutdown**. You must also stop the LoadMaster from the Azure WUI by clicking **Stop**.

c) To start the LoadMaster on the Azure WUI, click **Start**.

d) When the LoadMaster boots up, navigate to: **System Configuration > Interfaces** on the LoadMaster WUI and verify that two interfaces (**eth0** and **eth1**) are displayed under **System Configuration > Interfaces**.

```
eth0      Link encap:Ethernet  HWaddr 00:0d:3a:8d:4b:fe
          inet addr:192.168.1.4  Bcast:192.168.1.255  Mask:255.255.255.0
          inet6 addr: fe80::20d:3aff:fe8d:4bfe/64 Scope:Link
          UP BROADCAST NOTRAILERS RUNNING MULTICAST  MTU:1500  Metric:1
          RX packets:1143 errors:0 dropped:0 overruns:0 frame:0
          TX packets:1705 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:1000
          RX bytes:538178 (538.1 KB)  TX bytes:1254819 (1.2 MB)

eth1      Link encap:Ethernet  HWaddr 00:0d:3a:8d:4b:fe
          UP BROADCAST NOTRAILERS RUNNING SLAVE MULTICAST  MTU:1500  Metric:1
          RX packets:941 errors:0 dropped:0 overruns:0 frame:0
          TX packets:1713 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:1000
          RX bytes:459351 (459.3 KB)  TX bytes:1262421 (1.2 MB)

lo        Link encap:Local Loopback
          inet addr:127.0.0.1  Mask:255.0.0.0
          inet6 addr: ::1/128 Scope:Host
          UP LOOPBACK RUNNING  MTU:1500  Metric:1
          RX packets:1520 errors:0 dropped:0 overruns:0 frame:0
          TX packets:1520 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:1000
          RX bytes:1100982 (1.1 MB)  TX bytes:1100982 (1.1 MB)
```

e) You can also verify that two interfaces are active by checking performing an Ifconfig. To perform an Ifconfig, navigate to **System Configuration > Logging Options > System Log Files** and click **Debug Options**. On the **Debug Options** screen, click **Ifconfig**. This displays two interfaces with the same hardware address.

3.3.1.0.2 Add Multiple Interfaces to the LoadMaster

The Azure WUI does not allow interfaces with accelerated networking to be added. You must add the interface by using the Azure command line interface (CLI) or by using PowerShell.


You must run the command with the LoadMaster in a powered off state.

1. Create the interface using the Azure CLI similarly to the example below:


```
PS C:\Users\test> az network nic create --resource-group testdoc --name
myNic2 --vnet-name myVnet --subnet subnet2 --accelerated-networking true --
public-ip-address myPublicIp2 --network-security-group myNetworkSecurityGroup
--location eastus
```

3 Creating a LoadMaster for Azure VM

2. When the interface is created, you can add this interface to the LoadMaster when it is in a powered off state. Navigate to the **Networking** tab of the LoadMaster on the Azure WUI.



3. Click **Attach network interface**.



4. When the attachment is complete, both interfaces appear on the Azure WUI.

5. Restart the LoadMaster.

6. Verify that the interfaces are displayed under **System Configuration > Interfaces** on the LoadMaster WUI. The LoadMaster WUI should now display four interfaces.

You can also verify that four interfaces are active by checking performing an Ifconfig. To perform an Ifconfig, navigate to **System Configuration > Logging Options > System Log Files** and click **Debug Options**. On the **Debug Options** screen, click **Ifconfig**.

3 Creating a LoadMaster for Azure VM

```

eth0    Link encap:Ethernet HWaddr 00:0d:3a:8d:4b:fe
        inet addr:192.168.1.4 Bcast:192.168.1.255 Mask:255.255.255.0
        inet6 addr: fe80::20d:3aff:fe8d:4bfe/64 Scope:Link
        UP BROADCAST NOTRAILERS RUNNING MULTICAST MTU:1500 Metric:1
        RX packets:1102 errors:0 dropped:0 overruns:0 frame:0
        TX packets:1641 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:1000
        RX bytes:407988 (407.9 KB) TX bytes:1246784 (1.2 MB)

eth1    Link encap:Ethernet HWaddr 00:0d:3a:8c:3e:81
        inet addr:192.168.2.4 Bcast:192.168.2.255 Mask:255.255.255.0
        inet6 addr: fe80::20d:3aff:fe8c:3e81/64 Scope:Link
        UP BROADCAST NOTRAILERS RUNNING MULTICAST MTU:1500 Metric:1
        RX packets:68 errors:0 dropped:0 overruns:0 frame:0
        TX packets:27 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:1000
        RX bytes:8147 (8.1 KB) TX bytes:4702 (4.7 KB)

eth2    Link encap:Ethernet HWaddr 00:0d:3a:8d:4b:fe
        UP BROADCAST NOTRAILERS RUNNING SLAVE MULTICAST MTU:1500 Metric:1
        RX packets:864 errors:0 dropped:0 overruns:0 frame:0
        TX packets:1648 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:1000
        RX bytes:344516 (344.5 KB) TX bytes:1254164 (1.2 MB)

eth3    Link encap:Ethernet HWaddr 00:0d:3a:8c:3e:81
        UP BROADCAST NOTRAILERS RUNNING SLAVE MULTICAST MTU:1500 Metric:1
        RX packets:0 errors:0 dropped:0 overruns:0 frame:0
        TX packets:15 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:1000
        RX bytes:0 (0.0 B) TX bytes:3256 (3.2 KB)

lo      Link encap:Local Loopback
        inet addr:127.0.0.1 Mask:255.0.0.0
        inet6 addr: ::1/128 Scope:Host
        UP LOOPBACK RUNNING MTU:1500 Metric:1
        RX packets:1575 errors:0 dropped:0 overruns:0 frame:0
        TX packets:1575 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:1000
        RX bytes:1084369 (1.0 MB) TX bytes:1084369 (1.0 MB)

```

Unlike the single interface case where **eth0** and **eth1** are related, for multiple interfaces, **eth0** and **eth2** and **eth1** and **eth3** are related (with the same MAC address). **eth0** and **eth1** have the IP addresses, the other interfaces without the IP addresses are related by the **HWaddr** (the MAC address).

3.3.2 Recommended Pricing Tier

When creating a LoadMaster for Azure Virtual Machine, you must select a pricing tier. The recommended pricing tiers are listed in the table below.

If the relevant pricing tier is not displayed, click **View all**.

VLM Model	Recommended Pricing Tier
VLM-200	A1, A2, A3
VLM-2000	A2, A3, A4
VLM-5000	A3, A4, A5

VLM Model	Recommended Pricing Tier
VLM-10G	A7, A8, A9

3.4 Licensing and Initial Configuration

The following procedure will help you set up LoadMaster for Azure by ensuring appropriate licensing and basic configuration before you can create a Virtual Service and publish the required workloads:

1. Using a supported web browser, navigate to **https://<DNSName>:8443**.

Substitute <DNSName> with the DNS name you created in previous section.

2. Take the appropriate steps to acknowledge notification about the self-signed certificate to proceed.

3. The LoadMaster requires you to log in before you can proceed any further. The password used to log in will vary depending on whether you choose to use **Password** authentication or **SSH Public Key** authentication when creating the VM in the **Licensing Options** section:

- **Password:** Provide the username **bal** and the password which was set in the **Licensing Options** section.

Click **Continue**.

- **SSH Public Key:** Provide the default username **bal** and password **1fourall** to proceed. You are required to change the default password soon after.

4. You are presented with the End User License Agreement (EULA). You must accept the EULA to proceed further. Click **Agree** to accept the EULA.

5. After accepting the EULA, you are presented with a password change screen. Provide a secure password of your choice. Click **Set Password** to commit changes. The new password is effective immediately.

6. On the password notification screen, click **Continue**.

7. The LoadMaster requires you to authenticate with a new password. Enter **bal** in the user field and the new password in the password field. Click **Ok** to proceed.

8. Before using the LoadMaster, it must be licensed. For instructions on how to license the LoadMaster, refer to the **LoadMaster Licensing Feature Description** on the [Kemp Documentation Page](#).

When licensing a trial, you can usually only get a trial VLM-5000.

9. After licensing, you are given the opportunity to enable Kemp Analytics. With this feature, LoadMaster collects and sends usage data to Kemp for analysis. This data is strictly about product usage, enabled capabilities, and statistics. No sensitive user data, or traffic of any kind is either collected or communicated. To enable this feature, click **Enable Kemp Analytics**. To proceed without enabling this feature, click **Don't Enable Kemp Analytics**. For more information, visit <https://kemp.ax/KempAnalytics>.

10. You are then presented with the main menu and home screen of the LoadMaster.

Before you can create Virtual Services, you should create VMs that you are load balancing through LoadMaster for Azure. Ensure that your Network Security Group (NSG) is set up correctly depending on which services you are load balancing. The following section will provide some details on this topic.

4 Creating Virtual Services

The following steps describe how to create a Virtual Service on the LoadMaster for Azure.

1. Using a supported web browser, navigate to **https://<DNSName>:8443**. Substitute **<DNSName>** with the DNS name you created in the **Creating a LoadMaster for Azure VM** section.
2. Take the appropriate steps to acknowledge notification about the self-signed certificate to proceed further.

The certificate used by the WUI will take the public name used by Azure.

3. If prompted, log in to the WUI.
4. From the main menu, expand the **Virtual Services** section and click **Add New**.
5. In the Virtual Service parameters section, provide the following details:
 - a) **Virtual Address:** This field is pre-populated with the eth0 IP address:
 - i. If only one Network Interface Card (NIC) is present for the Virtual Machine - the LoadMaster is limited to a single IP. To create a Virtual Service, you must use the internal IP address of the LoadMaster VM. You can find the internal IP address in the VM's dashboard page.
 - ii. If more than one NIC is present in the Virtual Service, it is possible to use any of the internal IP addresses as the Virtual Service address.

Only the IP address on eth0 is connected to the public IP.

- b) **Port:** This must be the same port as the Private Port defined while creating the endpoint in earlier section.
 - c) **Service Name:** While optional, service name helps identify the purpose of the Virtual Service being created
 - d) **Protocol:** This must be the same as the protocol selected during creation of the endpoint in the earlier section.
6. Click the **Add this Virtual Service** button.

7. Expand the **Standard Options** section.

▼ Standard Options	
Force L7	<input checked="" type="checkbox"/>
Transparency	<input type="checkbox"/>
Subnet Originating Requests	<input type="checkbox"/>
Extra Ports	<input type="text"/> <button>Set Extra Ports</button>
Persistence Options	Mode: <input type="text" value="None"/>
Scheduling Method	<input type="text" value="round robin"/>
Idle Connection Timeout (Default 660)	<input type="text"/> <button>Set Idle Timeout</button>
Use Address for Server NAT	<input type="checkbox"/>
Quality of Service	<input type="text" value="Normal-Service"/>

Virtual Services in the LoadMaster for Azure may be set to transparent.

8. Configure the remaining virtual parameters as necessary. Use the Kemp LoadMaster guides from the Product Documentation section located on the Kemp website:

<http://kemptechnologies.com/documentation>


9. Add VMs being load balanced in the **Real Servers** section of the Virtual Service.

Repeat the steps above as necessary to create more Virtual Services on LoadMaster for Azure.


5 Deploying a LoadMaster Programmatically






If you want to deploy a LoadMaster outside of the portal, for example using a template or a script, you must first enable programmatic deployment of the offering in the portal. To do this, follow the steps below:

1. From the Azure Management Portal dashboard, click **Marketplace**.



2. In the menu on the left, click the **New** icon.



NAME	PUBLISHER	CATEGORY
 2 Gbps Load Balancer (Hourly)	KEMP Technologies Inc	Azure Certified
 20 Mbps Load Balancer (BYOL and Free)	KEMP Technologies Inc	Azure Certified
 10 Gbps Load Balancer (Hourly)	KEMP Technologies Inc	Azure Certified
 200 Mbps Load Balancer (Hourly)	KEMP Technologies Inc	Azure Certified
 5 Gbps Load Balancer (Hourly)	KEMP Technologies Inc	Azure Certified

3. Enter **Kemp** in the search bar.

5 Deploying a LoadMaster Programmatically

4. Click the desired Virtual Machine type.

Select a deployment model ⓘ

Resource Manager ▼

Create

Want to deploy programmatically? [Get started →](#)

5. Click the **Want to deploy programmatically?** link at the bottom.

SUBSCRIPTION NAME	SUBSCRIPTION ID	STATUS	
KEMPCorp	7bbfc9a3-3321-425c-8a76-1a55b2fd2218	Enable	Disable
<div>SaveDiscard</div>			

6. Select **Enable** and click **Save**.

You must repeat these steps for any other Virtual Machine types that you want to deploy programmatically.

References

While the instructions above provide a basic overview of how to deploy and configure LoadMaster for Azure, it is not designed to be a comprehensive guide to configure every possible workload. This section identifies some of many guides published on our resources section of our website. Unless otherwise specified, the following documents can be found at <http://kemptechnologies.com/documentation>.

Kemp LoadMaster, Product Overview

Web User Interface (WUI), Configuration Guide

CLI, Interface Description

RESTful API, Interface Description

Virtual Services and Templates, Feature Description

SubVSs, Feature Description

SSL Accelerated Services, Feature Description

Port Following, Feature Description

Content Rules, Feature Description

ESP, Feature Description

Quickstart Guide

HA for Azure, Feature Description

Licensing, Feature Description

You can find more documentation here: <http://kemptechnologies.com/documentation>

You can engage in community discussions on forums at:

<https://support.kemptechnologies.com/hc/en-us/community/topics>

Last Updated Date

This document was last updated on 27 July 2023.